

XRootD Configuration Reference

16-March-2021 Release 5.2.0 and above Andrew Hanushevsky



©2004-2021 by the Board of Trustees of the Leland Stanford, Jr., University All Rights Reserved Produced under contract DE-AC02-76-SFO0515 with the Department of Energy This code is open-sourced under a GNU Lesser General Public license. For LGPL terms and conditions see <u>http://www.gnu.org/licenses/</u>

1	Int	roduction	7
	1.1	Security Considerations	8
	1.2	Starting the xrootd Daemon	
	1.2.2	C	
	1.2.2	2 Passing Plug-In Command Line Arguments	16
	1.2.3	0 0	
	1.2.4		
		2.4.1 Environmental Information File	
•	1.2.5	1	
2		mework Directives by Category	
	2.1	Debugging	
	2.2	Monitoring	
	2.3	Networking	21
	2.4	Operational Environment	21
	2.5	Protocol support	21
	2.6	Security and TLS	22
	2.7	Tuning	22
~	C		
3	CO	mmon Framework Configuration Directives	23
3	Co 3.1	adminpath	
3		adminpath	23
3	3.1	adminpath	23 25
3	3.1 3.1.1	adminpath 1 Administrative Interface	23 25 26
3	3.1 3.1.3 3.2	adminpath 1 Administrative Interface allow	23 25 26 27
3	3.1 3.1.1 3.2 3.3	adminpath Administrative Interface allow homepath	23 25 26 27 29
3	3.1 3.2 3.3 3.4 3.5	adminpath Administrative Interface allow homepath tls (<i>required for</i> TLS) tlsca (<i>required for</i> TLS)	23 25 26 27 29 31
	3.1 3.2 3.3 3.4 3.5	adminpath Administrative Interface allow homepath tls (<i>required for</i> TLS) tlsca (<i>required for</i> TLS) oteric Framework Configuration Directives	23 25 26 27 29 31 35
	3.1 3.2 3.3 3.4 3.5 Esc	adminpath Administrative Interface allow homepath tls (<i>required for</i> TLS) tlsca (<i>required for</i> TLS) oteric Framework Configuration Directives buffers	23 25 26 27 29 31 35 35
	3.1 3.2 3.3 3.4 3.5 Esc 4.1	adminpath Administrative Interface	23 25 26 27 29 31 35 35 37
	3.1 3.2 3.3 3.4 3.5 Esc 4.1 4.2	adminpath Administrative Interface	23 25 26 27 29 31 35 35 37 41
	3.1 3.2 3.3 3.4 3.5 Esc 4.1 4.2 4.2.1	adminpath Administrative Interface	23 25 26 27 29 31 35 35 37 41 42
	3.1 3.2 3.3 3.4 3.5 Esc 4.1 4.2 4.2.1	adminpath Administrative Interface	23 25 26 27 29 31 35 35 37 41 42 42
	3.1 3.2 3.3 3.4 3.5 Esc 4.1 4.2 4.2.2 4.2.2	adminpath Administrative Interface	23 25 26 27 29 31 35 35 37 41 42 42 43
	3.1 3.2 3.3 3.4 3.5 Esc 4.1 4.2 4.2.3 4.3	adminpath Administrative Interface	23 25 26 27 29 31 35 35 37 41 42 42 43 43

	4.7	sched	. 51
	4.8	sitename	. 53
	4.9	tcpmonlib	. 55
	4.10	timeout	. 57
	4.11	tlsciphers	. 59
	4.12	trace	. 60
5	xro	ootd Directives by Category	. 63
	5.1	Data Access	. 63
	5.2	Data Integrity	. 63
	5.3	Debugging	. 63
	5.4	Monitoring	. 63
	5.5	Prepare Processing	. 63
	5.6	Security	
	5.7	Tuning	. 63
6	Co	mmon xrootd Configuration Directives	. 65
	6.1	export	
	6.2	seclib	
7			
7		oteric xrootd Configuration Directives	. 69
7	Ese		. 69 . 69
7	Es 7.1	oteric xrootd Configuration Directives async chksum	. 69 . 69 . 73
7	7.1 7.2	oteric xrootd Configuration Directives async chksum diglib	. 69 . 69 . 73 . 76
7	7.1 7.2 7.3	oteric xrootd Configuration Directives async chksum diglib 1 Authorizing digFS Access	. 69 . 69 . 73 . 76 77
7	7.1 7.2 7.3 7.3. 7.3. 7.3.	oteric xrootd Configuration Directives async chksum diglib 1 Authorizing digFS Access 2 Optional digFS Directives 3.2.1 addconf	. 69 . 73 . 76 77 80 80
7	7.1 7.2 7.3 7.3.7 7.3.7 7.3.7	oteric xrootd Configuration Directives async chksum diglib 1 Authorizing digFS Access 2 Optional digFS Directives 3.2.1 addconf 3.2.2 log	. 69 . 73 . 76 77 80 80 81
7	7.1 7.2 7.3 7.3. 7.3. 7. 7. 7. 7.3.	oteric xrootd Configuration Directives async chksum diglib 1 Authorizing digFS Access 2 Optional digFS Directives 3.2.1 addconf 3 Using digFS	. 69 . 73 . 76 77 80 80 81 82
7	7.1 7.2 7.3 7.3. 7.3. 7.3. 7.3. 7.3. 7.3. 7	oteric xrootd Configuration Directives async chksum diglib 1 Authorizing digFS Access 2 Optional digFS Directives 3.2.1 addconf 3.2.2 log 3 Using digFS fslib	. 69 . 73 . 76 77 80 80 81 82 . 83
7	 Ese 7.1 7.2 7.3 7.3.2 7.3.2 7.3 7.3.3 7.4 7.5 	oteric xrootd Configuration Directives async chksum diglib 1 Authorizing digFS Access 2 Optional digFS Directives 3.2.1 addconf 3.2.2 log 3 Using digFS fslib fsoverload	. 69 . 73 . 76 77 80 80 81 82 . 83 . 85
7	 7.1 7.2 7.3 7.3.2 7.3.2 7.3 7.3.2 7.4 7.5 7.6 	oteric xrootd Configuration Directives async	. 69 . 73 . 76 77 80 81 82 . 83 . 85 . 87
7	 Ese 7.1 7.2 7.3 7.3.2 7.3.2 7.3 7.3.2 7.4 7.5 7.6 7.7 	oteric xrootd Configuration Directives async chksum diglib 1 Authorizing digFS Access 2 Optional digFS Directives 3.2.1 addconf 3.2.2 log 3 Using digFS fslib fsoverload log mongstream	. 69 . 73 . 76 77 80 80 81 . 82 . 83 . 85 . 87 . 89
7	 7.1 7.2 7.3 7.3. 7.3. 7.3. 7.3. 7.4 7.5 7.6 7.7 7.8 	oteric xrootd Configuration Directives async chksum diglib 1 Authorizing digFS Access 2 Optional digFS Directives 32.1 addconf 3.2.2 log 3 Using digFS fslib fsoverload log mongstream monitor	. 69 . 69 . 73 . 76 77 80 80 81 . 82 . 83 . 85 . 87 . 89 . 93
7	 Ese 7.1 7.2 7.3 7.3. 7.3. 7.3. 7.4 7.5 7.6 7.7 7.8 7.9 	oteric xrootd Configuration Directives async chksum diglib 1 Authorizing digFS Access 2 Optional digFS Directives 3.2.1 addconf 3.2.2 log 3 Using digFS fslib fsoverload log mongstream monitor prep	. 69 . 69 . 73 . 76 77 80 80 81 . 82 . 83 . 83 . 85 . 87 . 89 . 93 . 99
7	 7.1 7.2 7.3 7.3. 7.3. 7.3. 7.3. 7.4 7.5 7.6 7.7 7.8 	oteric xrootd Configuration Directives async chksum diglib 1 Authorizing digFS Access 2 Optional digFS Directives 32.1 addconf 3.2.2 log 3 Using digFS fslib fsoverload log mongstream monitor	. 69 . 69 . 73 . 76 77 80 80 81 . 82 . 83 . 85 . 87 . 89 . 93 . 99 101

7.12 tı	race	105
8 Enal	oling HTTP Access	107
8.1 E	nabling HTTPS	109
8.1.1	Backward Compatibility and Overrides	111
8.2 D	Directives to Enhance HTTPS Access	111
8.2.1	desthttps	
8.2.2	gridmap	113
8.2.3	httpsmode	
8.2.4	secretkey	115
8.2.5	selfhttps2http	116
8.2.6	secxtractor	117
8.2.7	tlsreuse	118
8.2.8	Deprecated HTTPS Directives	119
8.2.8	8.1 cadir	119
8.2.8	8.2 cafile	120
8.2.8	8.3 cert	121
8.2.8	8.4 cipherfilter	122
8.2.8	8.5 key	123
8.3 C	Common Directives	124
8.3.1	embeddedstatic	124
8.3.2	exthandler	125
8.3.3	header2cgi	126
8.3.4	listingdeny	127
8.3.5	listingredir	128
8.3.6	staticpreload	129
8.3.7	staticredir	
8.3.8	trace	
9 Doct	ument Change History	133

1 Introduction

This document describes the e<u>X</u>tended <u>R</u>equest <u>D</u>aemon (**xrd**) configuration directives protocols that can be used with **xrd**: **cmsd**, **HTTP**, and **xrootd**. It also includes the directives for the **xrootd** daemon that can run **xroot** and **HTTP** protocols. The **cmsd**-specific directives are described in a separate reference manual.

The **xrd** is a framework that can dynamically support multiple **TCP/IP** application service layer protocols. It is designed to provide a high performance environment for application services. The **xrd** is a generalized framework and it makes its primary decision on which protocol to support based on the name given to the executable. Currently, the following executable names are fully supported:

- **cmsd** daemon for the **cms** server clustering protocol, and
- **xrootd** daemon for **xroot** and other related protocols.

Configuration directives come from a configuration file. Directives are prefixed by the component acronym they apply to, as shown in the following table. This makes creating a single configuration file for all services possible.

Component	Purpose
acc	Access control (i.e., authorization)
cms	Cluster Management Services
frm	File Residency Manager
ofs	Open File System
oss	Open Storage System (i.e., file system implementation)
pfc	Proxy File Cache
pss	Proxy Storage Service
sec	Security authentication
xrd	Extended Request Daemon
xrootd	The xroot protocol implementation.
http	The HTTP protocol implementation.
all	Applies the directive to all of the above components.

Records that do not start with a recognized identifier are ignored. This includes blank record and comment lines (i.e., lines starting with a pound sign, #). This guide documents the **all**, **http**, **xrd**, and **xrootd** configuration directives (i.e., the un-shaded rows). Other directives are documented in supplemental references specific to the component they deal with.

The location of the configuration file is specified on the **xrootd** command line. Refer to the reference manuals for other components on how they locate their respective configuration files.

Refer to the manual "**Configuration File Syntax**" on how to specify and use conditional directives and set variables. These features are indispensable for complex configuration files usually encountered in large installations.

1.1 Security Considerations

The **xrd** framework relies on the loaded protocol(s) for strong authentication (e.g., Kerberos, GSI, etc.). Therefore, security is a protocol issue. The **xroot** protocol provide strong authentication should you choose to use it. Refer to each protocol on how to configure strong authentication.

The **xrd** framework does provide host-based authentication. While this type of authentication can be subverted in a number of ways, it still is a practical mechanism for installations that do not need strong authentication. The **allow** directive can be used to restrict the range of hosts that can connect to the daemon. This security can be used together with any protocol-provided security.

Because the **xrd** framework does not intrinsically provide strong authentication; you *should not run* **xrootd** *as super-user* (i.e., **Unix** root). Any attempt to do so without indicating that you *really* want to run super-user (see the **-R** command line option) will cause the program to exit.

1.2 Starting the xrootd Daemon

Use the following command to start the **xrd**-based **xrootd** daemon:

```
xrootd [ options ] [ path [ path [ . . . ] ] [piargs]
options: [-c cfn] [-l largs]
        [-k {num | sz{k|m|g} | sig}] [esoteric]
esoteric: [{-a | -A} apath] [-b] [-d] [-h] [-I {v4 | v6}]
        [-n name] [-R user] [-s pfn] [-S site]
        [{-w | -W} hpath] [-z] [devopts]
devopts: [-L protlib] [-p {port | any}] [-P protocol]
largs: [=]fn | - |
        @lib[,bsz=sz][,cse={0|1|2}][,logfn=[=]fn]
sig: fifo|hup|rtmin|rtmin+1|rtmin+2|ttou|winch|xfsz
piargs: -+[tag] [args] [piargs]
```

Parameters

path An absolute file system path prefix. All requests will be restricted to files with this prefix. You may specify any number of path prefixes. If no path is specified, operations will be restricted to paths starting with **/tmp**.

Options

-c *fn* The name of the configuration file. If one is not specified, no configuration file is processed.

Configuration

-1 [=] fn

Specified how messages are to be handled. Options are:

- *fn* Directs messages and any trace output to the indicated file, *fn*, possibly qualified by the instance name (see the <u>fencing section</u>). If *fn* is a dash (-), output is sent to standard error; the default.
- *=fn* Same as fn but the *fn* is not qualified by the instance name, if any. This allows log files to be handled in an arbitrary manual way. For more information see the section on <u>fencing</u>.
- @lib Directs messages to a plug-in that is defined in the shared library specified by *lib* (see the section on <u>log file plug-ins</u>). Additional comma-separated parameters may follow *lib*, as follows:
 - **bsz=**szSpecifies the size of the speed matching buffer. The
default is 64K. Messages are placed in the buffer and
then forwarded to the plug-in as time permits. A value of
0 disables speed matching and messages are handed off
to the plug-in as they occur. See the section on log file
plug-ins for more information. A positive value less than
8K is forced to be 8K. The maximum allowed in one
megabyte. The sz may be suffixed by k or m to indicate
kilobytes or megabyte, respectively.

cse={0|1|2} Specifies how standard error output should be handled:

- 0 Does not capture standard error output. All such output is sent to the **logfn** destination, if specified, or is otherwise lost. This is the default.
- Captures standard error but only forwards it to the logging plug-in if it starts with a standard time stamp. This option may cause an infinite loop. Refer to the <u>logging plug-in section</u> for more information.
- 2 Captures standard error output and forwards it to the logging plug-in without inspection. Refer to the <u>logging plug-in section</u> for more information.
- logfn=[=]fnSpecifies that messages are also to be routed to a local log
file. The parameter is identical to that described above.
To use standard error, specify a dash (-) for fn.

-**k** num $\mid sz\{\mathbf{k} \mid \mathbf{m} \mid \mathbf{g}\} \mid sig$

Keep no more than *num* old log files. If *sz* is specified, the number of log files kept (excluding the current log file) is trimmed to not exceed *sz* bytes. The *sz* must be suffixed by **k**, **m**, or **g** to indicate **k**ilobytes, **m**egabyte, or **g**igbytes, respectively. If a *sig* value is specified (i.e. **hup** etc), then an external program is expected to handle log file rotation (e.g. logrotate). Except for **fifo**, the argument specifies signal that causes the daemon to close and re-open the log file to allow rotation to occur. When fifo is specified, the daemon waits for data to appear on a fifo whose path is identical to the log file path but whose name is prefixed by a dot. Refer to the notes for manual rotation caveats.

Esoteric Options

 $\{-a \mid -A\}$ apath

Specifies the default administrative path and can be overridden by the **adminpath** directive in the configuration file. When **-A** is specified group write access is allowed (see the **adminpath** <u>directive</u> **group** option for details).

-b Runs the program in the background. You should also specify -1.

-d Turns on debugging. Warning! This severely impacts performance.

-h Displays help information.

-I $\{v4 \mid v6\}$

Restricts the server's internet address protocol. When **v4** is specified, only hosts with IPV4 addresses can connect or be connected to. When **v6** is specified, the default, hosts using IPV6 or IPV4 addresses can connect or be connected to. This option is only useful for systems that have misbehaving IPV6 network stacks. The default is established by the network interface configuration on the machine at the time the program starts.

-n name

Assigns *name* to the **xrootd** instance. By default, the **xrootd** instance is unnamed. See the notes on how to use this option.

-R user

The user name or numeric uid of the *user* whose effective identity is to be assumed. See the usage notes for more information. The specified user may not have super-user privileges. This option may *not* be specified unless the program is running as super-user.

-s *pfn* Specifies the name of the file that is to hold the process id upon start-up.

-S *site* Specifies a 1- to 15-character site name that is to be included in monitoring records. The name may only contain letters, digits and the symbols "_-:."; any other characters are converted to a period.

{-w | **-W**} *hpath*

Specifies the default home path; i.e. the current working directory during execution. If it is not specified on the command line, it can be specified by the **homepath** directive in the configuration file. When **-W** is specified group read access is allowed (see the **homepath** <u>directive</u> **group** option for details). The *hpath* is extended by any specified instance name (i.e. **-n** option). The path is created should it not exist.

- -z provides microsecond resolution for log file message timestamps.
- -+ provides a mechanism to pass command line arguments to plug-ins. See the section "Passing Plug-In Command Line Arguments" for more information.

Developer Options

-L protlib

Specifies the shared library that holds the implementation of the default protocol specified by the **–P** option.

-p port

The **TCP** port, or service name associated with a port, that **xrootd** is use for new connections. The default is "**xrootd**" or port **1094**, if the **TCP** service **xrootd** cannot be found /etc/services.

-p any

Uses any available port.

-P protocol

The name of the default protocol. Use this option when the name of the executable differs from the name of the default protocol. You may need to specify the –L option as well. See the notes for more information.

Defaults Arguments

-1 - -I v6 -p xrootd -P executable_name /tmp

General Notes

- For security purposes, only files in /tmp are allowed to be accessed unless you specify otherwise. You may specify other paths either on the command line or using the xrootd export configuration directive.
- 2) Do *not* prefix any export *path* with the **oss localroot** directive path, if any.
- 3) If a log file is specified without a signal -k option, the file is closed at midnight, renamed to have a date suffix (i.e., *fn.yyyymmdd*) and possible sequence number (i.e. *fn.yyyymmdd.n*), and a new log file is opened. When a signal value is specified, log files are not automatically renamed at midnight. Instead an external program must be used to properly rotate log files. Make sure to choose a signal that is *not* in use by *any* plug-in. If unsure, choose one of the obscure signal names and monitor for any odd behavior. Otherwise, use the **fifo** option. Be aware that on some non-Linux platforms the fifo file descriptor may leak.
- 4) When **fifo** is specified the fifo file name must not exists or exist as a fifo file. A simple "**echo x** >> *lpathl.lfn*" causes the logfile to close and reopen.
- 5) The *sig* names should *not* be prefixed by "**sig**" or "**SIG**".

Notes on Esoteric Options

- 1) The default port service name, default protocol, and *pidfile* name is normally determined by the prefix-name of the executable. The prefixname is defined to be all of the characters in the base filename (i.e., the directory path removed) up to but not including the first dot in the name, if any. If the name starts with a dot, the prefix-name is the complete base filename.
- 2) The way the prefix-name is derived allows you to maintain several versions of a particular **xrd** executable (e.g., **xrootd** and **xrootd.debug**) without changing the intrinsic way default names (e.g, protocol) are determined.
- 3) The built-in protocol name for **cmsd** is **cms** and for **xrootd** is **xroot**.
- 4) The **–n** option allows you to run multiple instances of the **xrootd** on the same machine. See the next section on instances and fencing.
- 5) The **-b** option forces the program into the background. If **-l** is not specified; all output messages are discarded.
- 6) When **-b** is specified, the program fails if it cannot write the **pid** file.

- 7) The -R option allows the program to run under the super user's account. This is allowed because the effective user is set to specified user and the effective group to user's primary group. Thus, the program is not *effectively* running as super-user. However, the real and saved user ids may still be "root", depending on how the program was started.
- 8) The **-R** option provides a minimal increase in security since it is possible for a loaded protocol to switch back to super user mode. You should not use the **-R** option unless absolutely necessary.
- 9) Warning: Command line options, except for -a and -s, over-ride corresponding configuration file directives. For -s the pid file is written to the desired location in addition to the location specified by the pidpath directive.

Notes on Developer Options

- 1) You must use the **–P** option to set the default protocol name as well as other related naming aspects (e.g., port service name) when the name of the executable does not correspond to the name of the default protocol.
- 2) Use **-p** any for protocols that manage their own port numbers. This is the case for redirection target **xrootd/cmsd** combinations. Only the initial point of contact needs a well-known port number. All other connections between clients and servers are routed using whatever port numbers are currently in effect. This allows you to keep a simple configuration file for servers and to run more than one server on the same machine without worrying about conflicting port numbers.

Example

xrootd -c /opt/xrootd/xrootd.cf

1.2.1 Multiple Instances and Automatic Fencing

You can run multiple instances of **xrootd** on the same physical machine. This is useful when you want to overlay more than one cluster on top of a file system (e.g. production and test). In order to prevent instances from interfering with each other, you must provide each **xrootd** that is running on the same hardware a unique instance name. One of the daemons need not have an instance name as it assumes the name "anon" (i.e. anonymous).

Once an instance name is assigned to a daemon using the **–n** option, the system automatically fences in the daemon so that it does not interfere with any other **xrootd** processes running with it. Automatic fencing consists of threse actions:

- The instance name is suffixed to the adminpath to create a unique location for temporary server files. For instance, if –n is not specified, xrootd creates /tmp/.xrootd/admin as the path for the administrative interface. If "-n test" is specified, xrootd creates /tmp/test/.xrootd/admin instead. Even the path specified with the adminpath configuration directive is modified.
- The instance name is used to create a new directory in the current working directory. The current working directory is changed to this newly created path. So, if "/home/xrootd" is the current working directory and "-n test" is specified; the current working directory becomes "/home/xrootd/test". This allows core files to be segregated by instance name.
- The instance name is automatically inserted into the log file path specified via the -l command line directive to create a unique location for server log files. For instance, if "-l/var/adm/xrootd/xrd.log" is specified along with "-n test", xrootd modifies the -l argument to be /var/adm/xrootd/test/xrd.log.

Automatic fencing of log files may, for some installations, run counter to the way log files are commonly handled. You can disable fencing of log files by prefixing the log file path by an equals sign. However, you are then responsible to make sure that each instance uses a different log file path or name.

Much of this functionality has been subsumed into containerized frameworks. However, the functionality described here is still supported in the cases where containerization either does not provide the desired performance or is inconvenient thus making host-based applications becomes an imperative.

1.2.2 Passing Plug-In Command Line Arguments

You can pass command line arguments to various plug-ins that support the feature using the **-+** option. The option must be specified after all **XRootD** options and parameters as plug-in arguments are stripped from the command line. For example,

xrootd [*options*] [*path* [*path* [. . .]] **-+mypi** *arg1 arg2* **-+urpi** *arg3*

places a pointer to the vector containing "argv[0] *arg1 arg2* 0" into the internal environment passed to the plug-in using the variable "**mypi.argv****" and the count in "**mypi.argc**" (i.e. 3). Similarly, "argv[0] *arg3* 0" are pointed to by "**urpi.argv****" with the count in "**urpi.argc**" (i.e. 2). If no tag is specified, the leading prefix is missing (i.e. the variables are ".**argv****" and ".**argc**"). Note that argv[0] is the actual value of argv[0] (i.e. the executable name) passed to **XRootD**.

It is up to the plug-in to extract the appropriate arguments using a documented tag. Tag values that start with "**xrd**" should not be used as these are reserved for plugins normally distributed with the **XRootD** package.

1.2.3 Log File Plug-Ins

XRootD allows you to specify a plug-in to handle messages that would otherwise be sent to a regular file or standard error. You do this using the '@' qualifier with the **–1** option. Logging messages is a critical function in the server and any delay will severely impact server performance. The default logging path is very efficient and any plug-in placed in the path should be just as efficient. To help, a speed matching buffer is used to minimize plug-in vagaries. However, if you choose to not use a speed matching buffer (i.e. a **bsz** of zero for synchronous operation) then the plug-in becomes the choke point in server performance.

You may also choose to capture standard error output using the **cse** parameter. However, this option will result in an infinite loop if your logging plug-in writes to standard error for any reason. This may be mitigated by specifying **cse=1** which only sends standard error output to the plug-in if it starts with a timestamp of the form "**yymmdd hh:mm:ss**". All debugging output starts with such a timestamp.

The details on how you write a log file plug-in is detailed in the **XrdSysLogPI.hh** header file. It is important to realize that if you use the **XrdSysLogger** object to route a message from your plug-in, an infinite loop will result. Additionally, one log file plug-in is used for all **XrdSysLogger** instances.

1.2.4 Files created by xrootd

Default File	Changed by	Contents
<stderr></stderr>	-l and -n command line	Informational and error
	options	messages
/tmp//[name/].xrootd/	-n command line option	Directory for various server-
	and the adminpath	related files.
	directive	
<cwd>//[name/]core[.pid]</cwd>	-n command line options	Core file
/tmp/[name/]exec.pid	pidpath and -n option	Holds the process id
/tmp/exec.name.env	adminpath and –n option	Holds environmental
		information (see next section).

The following directories and files are created by **xrootd**:

1.2.4.1 Environmental Information File

The daemon writes environmental information in the directory specified by **adminpath** directive, or its default. This information can be used to automatically collect all relevant information about a daemon to facilitate automatic problem resolution.

The environmental file is named "*exec.name.***env**" where *exec* is the executable's name and *name* is the instance name (i.e. **-n** option) and **anon** if no instance name was specified. The format of the information is shown below. When parsing this information, you should not depend on the order shown below.

 $pid=\!\mathit{pid}\&host=\!\mathit{host}\&inst=\!\mathit{inst}\&ver=\!\mathit{ver}\&home=\!\mathit{hpath}\&cfgfn=\!\mathit{cfgfn}\&cwd=\!\mathit{cwd}\&logfn=\!\mathit{logfn}$

Parameters

- *cfgfn* The configuration file used.
- *cwd* The current working directory.
- *host* The host name.
- *hpath* The current working directory.
- *inst* The instance name.*logfn* The log file being used.*pid* The process id.
- ver The version string

These are the minimal elements. Additional elements may be added by specific protocols.

1.2.5 Exported Environment Variables

The following table shows the environment variable exported by **xrootd**. These may be used by external programs and plug-ins, as needed. They should never be modified.

XRD Variable	Contents
XRDADMINPATH	Is the directory for administrative files (i.e. all.adminpath)
XRDCONFIGFN	The effective administrative path used for server management
	files.
XRDDEBUG	Set to one when the –d command line option is specified.
XRDHOST	The current host's DNS name.
XRDINSTANCE	Is the string of the form "execname instance@hostname". Where
	<i>execname</i> is the executable's name, <i>instance</i> is the name
	specified via – n or anon if no instance name was specified,
	and <i>hostname</i> is the current host's DNS name.
XRDLOGDIR	Is the directory where log files are written.
XRDNAME	The name specified via –n or anon if no instance name was
	specified.
XRDPROG	The executable's name.
XRDSITE	The site name specified either via the –s command line option
	or the all.sitename directive.

If the standard **cms** client plug-in is being used, the following additional environment variables are exported.

CMS Variable	Contents
XRDCMSMAN	The space separated list of managers for this host each in
	the form of "host:port".
XRDCMSCLUSTERID	The globally unique cluster identification for this host.

If the standard **ofs** plug-in is being used, the following additional environment variables are exported.

OFS Variable	Contents
XRDROLE	The effective value specified on the all.role directive.
XRDTPC	Is set when TPC (Third Party Copy) has been configured and
	represents the version number of the protocol. If the first
	character is a plus sign, authentication is required.

If the standard **oss** plug-in is being used, the following additional environment variables are exported.

OSS Variable	Contents
XRDN2NLIB	The path and name of the name-to plug-in, if specified via
	the oss.namelib directive.
XRDRMTROOT	The local root path specified by the oss.remoteroot directive.
XRDLCLROOT	The local root path specified by the oss.localroot directive.
XRDOSSQUOTAFILE	The name and location of the file handling disk space
	quotas.
XRDOSSUSAGEFILE	The name and location of the file handling disk space usage.

If the standard **xrootd** protocol plug-in is being used, the following additional environment variables are exported.

XROOTD	Contents
Variable	
XRDOFSLIB	The path and name of the OFS plug-in specified by the
	xrootd.fslib directive.
XRDMONRDR	If monitoring is enabled, how often server identification
	records are sent.

2 Framework Directives by Category

This section provides a guide to **xrd** directives by category that is helpful when you need to address a specific requirement.

2.1 Debugging

xrd.trace Specify which framework activities are to be traced.

2.2 Monitoring

xrd.report	Specify which execution summary statistics are to be gathered and
	where they are to be sent.
all.sitename	Specify the name of the site to be used for monitoring purposes.
xrd.tcpmonlib	Specify the plug-in to be used to collect and report specialized TCP
	connection statistics.

2.3 Networking

xrd.network Specify network parameters such as **DNS** usage, interfaces, keepalive characteristics, and routing.

2.4 Operational Environment

all.adminpath	Specifies the location of runtime files used for administrative
	purposes.
xrd.homepath	Specifies the location of the working directory during execution.
all.pidpath	Specifies where the file containing the server's process id should be
	created.

2.5 Protocol support

xrd.portSpecifies the default port number for incoming requests.xrd.protocolLoad additional protocols such as HTTP.

2.6 Security and TLS

xrd.allow	Restricts hosts that can connect to the server.
xrd.tls	Specify the location of the server's host certificate.
xrd.tlsca	Specify the location of CA certificates and CRLs.
xrd.tlsciphers	Specify allowable TLS ciphers.

2.7 Tuning

xrd.buffers	Limit the amount of memory used for data buffers.
xrd.sched	Specify execution parameters such as core file creation, default stack
	size, and threading.
xrd.timeout	Specify various connection handling timeout parameters

3 Common Framework Configuration Directives

3.1 adminpath

all.adminpath path [group]

Function

Specify the location of protocol-specific files for administrative purposes.

Parameters

path The absolute path to a directory that is to hold protocol-specific files. The path should be no longer than 76-characters. See the notes for details.

group

Allows read/write group access to any named sockets created in the *path*. By default, only the owner can use such sockets.

Default (see warning in the notes) /tmp

Notes

- 1) The **adminpath** directive allows you to specify the location of the local **TCP** sockets used for the command-line administrative functions along with special directories that are needed to handle protocol specific features.
- 2) Use the **-a** or **-A** command line option to set the defaults for the **adminpath** directive.
- 3) If -n is specified on the command line, a subdirectory corresponding to the instance name (i.e., -n argument) is created in *path*, if one does not exist. This becomes the new *path*. This allows <u>fencing</u> multiple daemons running on the same node.
- 4) Warning: if idle /tmp directories and socket files are automatically deleted by the system, you *should* specify a path other than /tmp. Be aware if neither –a command line option nor the adminpath directive is specified, the default becomes /tmp. External removal of files stored in the adminpath may lead to server failure.

- 5) When specifying an **adminpath**; be cognizant that the program may be containerized and the path may not be suitable for that environment. Confer with your system administrators on what the suitable path should be if the program will run in a container.
- 6) Local **TCP** socket names are limited to 108 characters. Up to 32 characters are needed to define actual socket files; leaving 76 characters that may be specified for the *path*.
- 7) The following steps are taken when creating a **Unix** named socket in path:
 - The subdirectory **.xrd** is created in *path* and
 - the **cmsd** daemon creates subdirectory .**olb** while
 - the **xrootd** daemon creates subdirectory **.xrootd** in *path*.
 - Mode bits for these directories are set to 0700 (rwx for owner). If the directories already exist, the mode settings are reset to correspond the to the **adminpath** directive.
 - If **group** was specified, the mode setting is extended to 0770 (rwx for owner and group).
 - If the directories already exist, the mode settings are reset to correspond the to the **adminpath** directive specification.
 - Server, manager, and supervisor **cmsd**'s create stream sockets named "**olbd.admin**", "**olbd.nimda**", and "**olbd.super**" in the **.olb** subdirectory, respectively. These sockets are used for administrative communication.
 - Server and manager **cmsd**'s respectively create datagram socket named "**olbd.notes**" and "**olbd.seton**" in the **.olb** subdirectory. These sockets are used for external notifications.
 - The **xrootd** daemon creates a **Unix** named socket with the name "**admin**" in the **.xrootd** subdirectory.
- 8) The **adminpath** value is passed to all protocols so that they can create their respective administrative files in *path*. However, for the **cmsd** only, you may specify an exception by using the **cms.adminpath** directive to create a completely different path for its files.
- 9) Refer to the <u>section</u> "Administrative Interface" for details on how to use the **Unix** named socket created by various protocols and daemons.
- 1)

Example

all.adminpath /var/adm/xrd group

3.1.1 Administrative Interface

The **adminpath** directive is used to construct the path where local **TCP** sockets, called named sockets, are created. These sockets are used to communicate requests and receive responses via the administrative interface. Unix domain sockets function identically as INET domain sockets. The only differences are in how the socket is created and the domain in which it operates. Care should also be given as to who creates the socket. Following the next steps will allow the successful use of the administrative interface.

- 1. Wait until the server creates that the socket file (e.g., "/tmp/.xrootd/admin" or "/tmp/.olb/notes"). This can be done by polling for the socket using **stat()**.
- 2. Create a stream socket using **socket(PF_UNIX, SOCK_STREAM, 0**)
- Properly fill out the sockaddr_un structure with the path name of the socket (e.g., "/tmp/.xrootd/admin"). This structure is normally defined in the <sys/un.h> include file.
- 4. Issue a **connect()** call to connect the newly created socket to the path.
- 5. Use **write()** to issue requests to the server and **read()** to read responses.

The administrative protocol used for the socket interface is defined elsewhere.

3.2 allow

xrd.allow { host | netgroup } name

Function

Restrict the hosts that can connect to **xrootd**.

Parameters

host name

The DNS host name allowed to connect to **xrootd**. Substitute for *name* a host name or IP address. A host name may contain a single asterisk anywhere in the name. This lets you allow a range of hosts should the names follow a regular pattern. IP addresses may be specified in IPV4 format (i.e. "a.b.c.d") or in IPV6 format (i.e. "[x:x:x:x:x]").

netgroup name

The NIS netgroup allowed to connect to **xrootd**. Substitute for *name* a valid NIS netgroup. Only hosts that are members of the specified netgroup are allowed to connect to **xrootd**.

Defaults

None. If **allow** is not specified, any host is allowed to connect.

Notes

- 1) You may specify any number of hosts and netgroups. Any host matching a specified name or is a member of a specified netgroup is allowed to connect to **xrootd**.
- 2) **Warning!** Using hostname based security relies on the security of the DNS server and the inability of other hosts spoofing and successfully using the "allowed" IP addresses. The two security assumptions have severe limitations.

Example

xrd.allow host objyana*.slac.stanford.edu

3.3 homepath

xrd.homepath path [group]

Function

Specify the location of the current working directory.

Parameters

path The absolute path to a directory that is to be used as the working directory.

group

Allows read group access to path. B

Default

Whatever is the directory on start-up.

Notes

- 1) Use the **-w** or **-W** command line option to set the home path. When the home path is set on the command line, it cannot be overridden with the **homepath** directive.
- If -n is specified on the command line, a subdirectory corresponding to the instance name (i.e., -n argument) is created in *path*, if one does not exist. This becomes the new *path*. This allows <u>fencing</u> multiple daemons running on the same node.
- 3) When specifying a homepath; be cognizant that the program may be containerized and the path may not be suitable for that environment. Confer with your system administrators on what the suitable path should be if the program will run in a container.

Example

all.homepath /var/run/xrd group

3.4 tls (required for TLS)

```
xrd.tls cpath [ kpath ] [ options ]
```

```
options: [[no]detail] [hsto to{h|m|s]
```

Function

Configure transport layer security (TLS).

Parameters

- *cpath* Specifies the absolute path to the **x509** certificate file to use for **TLS**. The certificate must be in **PEM** format. The file may only be written by the owner of the file.
- *kpath* Specifies the absolute path to the certificate's **x509** private key file to use for **TLS**. The key must be in **PEM** format. The file may only be read and written by the owner of the file. If *kpath* is not specified then the certificate file must contain the key.

[no]detail

When **detail** is specified, detailed **TLS** trace back messages are printed along with explanatory messages. The **nodetail** option suppresses the **TLS** trace back messages. The default is **nodetail**. See the notes why this is so.

to Specifies the maximum amount of time a **TLS** handshake is allowed to take before the connection is closed. The *to* value may be suffixed by **h** for hours, **m** for minutes, or **s** for seconds, respectively; otherwise, the *to* value defaults to seconds. There is no default time limit for the **TLS** handshake.

Defaults

TLS is not configured and cannot be used. See individual options for the defaults should you configure **TLS**.

Notes

1) Normally, a host certificate should be used because the client can use it to validate that it connected to the intended host.

- 2) If you specify the **tls** directive then you must specify the **tlsca** directive as well.
- 3) Most **TLS** trace back messages do not provide any more information than the companion explanatory messages and, as such, is only useful for debugging purposes. This is why **nodetail** is the default. However, if you enable **TLS** tracing using the **xrd.trace** directive, **detail** is enabled regardless of what is specified.

Example

```
xrd.tls /etc/security/xrootd/hostcert.pem
```

3.5 tlsca (required for TLS)

```
xrd.tlsca noverify | {certdir | certfile} path [options]
options: [crlcheck {all | external | last}]
[log {failure | off}] [[no]proxies]
[refresh rint[h|m|s]] [verdepth vdn]
```

Function

Configure client certificate verification for transport layer security (TLS).

Parameters

noverify

Disables client certificate verification. All subsequent parameters, if any, are ignored.

certdir path

Specifies the absolute path of the directory containing trusted Certificate Authority certificates that can be used to verify client certificates. Each file in the directory may only contain a single certificate in **PEM** format. Naming conventions are those required by the version of **OpenSSL** being used. The directory may only be written to by the owner of the directory.

certfile *path*

Specifies the absolute path to the file containing one or more trusted Certificate Authority certificates that can be used to verify client certificates. The certificates in the specified file are used first before an attempt is made to find an appropriate certificate in **certdir**, if specified. The file must be in **PEM** format. The file may only be written to by the owner of the file.

crlcheck

Specifies the certificate revocation list (crl) is to be handled. Choose one of the following:

all - apply **crl** checking to the complete certificate chain.

external - **crl** application is handled by an external plug-in (the default).

last - apply **crl** checking only to the last certificate in the chain.

Specifies logging requirements. Logging messages are written to the log file. log Choose one of the following: failure - log failed verifications (the default).

off - verification failures are not to be logged.

- vdn Specifies the verification depth. Should the client present a certificate chain, up to the last vdn certificates are verified. Specify a value between 1 and 256, inclusive. The default is 9.
- rint Specifies the refresh interval. Suffix the value with **h** for hours, **m** for minutes, or **s** for seconds (the default). The default is **8h** (eight hours).

Defaults

xrd.tlsca crlcheck external log failure proxies refresh 8h verdepth 9

Notes

- 1) You may specify both a directory and a file. The certificates in the **certifie** will be searched before any certificates in certdir.
- 2) If *all* the loaded protocols use strong authentication (e.g. Kerberos, GSI, or SSS) client certificate verification is not necessary as the client will be verified using a strong authentication mechanism and the client's certificate will only be used to establish a TLS connection.
- 3) Certain protocols require certificate verification (e.g. **HTTPS**). If you enable one of these protocols you should enable verification overall to avoid specifying protocol specific directives that duplicate ones that could be specified using the **tlsca** directive.
- 4) In the absence of strong authentication, you should always verify client certificates. Generally, you should always verify client certificates. This is why the directive requires that you make an explicit choice.
- 5) All of the certificates in the directory, as well as the file, must in a format that is recognized by the version of **OpenSSL** being used.

6) If you use a **certdir** be aware that **OpenSSL** requires that the **c_rehash** utility be run after the certificates in the directory are updated. This introduces a race condition between refreshes and updates to the directory and may produce verification failures should a refresh occur while the directory is being updated. You can avoid this problem by making sure that changes to the directory are visibly done in an atomic fashion.

Example

xrd.tlsca certfile /etc/security/xrootd/cacerts.pem

4 Esoteric Framework Configuration Directives

4.1 buffers

xrd.buffers memsz[k | m | g] [rint[m | s | h]]

Function

Limits the amount of memory to be used to data buffers.

Parameters

memsz

The maximum number of bytes to be used for data buffers. The *memsz* can be suffixed by **k**, **m**, or **g** to indicate **k**ilo-, **m**ega-, or **g**iga-bytes; respectively. The default is to use up to 12.5% (one-eight) of the configured memory of the machine.

rint The interval between buffer pool readjustments. Specify a number, optionally suffixed by **m** for **m**inutes, **s** for **s**econds (the default), or **h** for **h**ours. The default is every 20 minutes.

Defaults

xrd.buffers memsz 20m

Notes

- 1) The allotted memory for buffers is independent of any other memory allotment to the daemon.
- 2) Data buffers in the pool are periodically readjusted to reflect the actual working needs of the daemon. The *rint* interval controls how frequently this adjustment occurs. The default value is usually the best value.

Example

xrd.buffers 512M

4.2 network

```
xrd.network [buffsz blen[k | m | g]] [cache sec]
    [[no]dnr] [[no]dyndns]
    [kaparms idle[,itvl[,cnt]] [[no]keepalive]
    [routes {split|common|local} [use if1[,if2]]]
    [[no]rpipa] [tls]
```

Function

Specify network parameters.

Parameters

buffsz blen

The buffer size to be set for each connected socket. The *blen* can be suffixed by **k**, **m**, or **g** to indicate **k**ilo-, **m**ega-, or **g**iga-bytes; respectively. The default is determined by the operating system.

cache sec

The maximum number of seconds that an address to hostname translation can be locally cached for future use. See the notes on its interaction with **dyndns**. The *sec* can be suffixed by **s**, **m**, **h** or **d** to indicate **s**econds, **m**inutes, or **h**ours, or **d**ays; respectively. The default is 3 hours.

- **dnr** Uses Domain Name Resolution to convert IP addresses to host name for connecting clients. Host names are displayed in various messages.
- **nodnr** Avoids using Domain Name Resolution to convert IP addresses to host name for connecting clients. Client IP addresses are displayed in various messages.

dyndns

The network uses a Dynamic **DNS** for name resolution. See the section on <u>Dynamic DNS</u> for information on when you should specify this option. See the notes on its interaction with **cache**.

nodyndns

The network uses a standard **DNS** whose name entries are stable. This is the default.

kaparms idle[,itvl[,cnt]

Specifies **TCP keepalive** parameters. The **kaparms** option is only effective for **Linux**. Up to three parameters may be specified. Omitted parameters, as well as parameter values of zero, use the system default. The parameters are:

- *idle* The time the connection needs to remain idle before **TCP** starts sending **keepalive** probes. The *idle* value may be optionally suffixed by **m** for **m**inutes, **s** for **s**econds (the default), or **h** for **h**ours.
- *itvl* The time between individual keepalive probes. The *itvl* value may be optionally suffixed by m for minutes, s for seconds (the default), or h for hours.
- *cnt* The maximum number of **keepalive** probes **TCP** should send before dropping the connection.

keepalive

Uses the operating system's keep-alive mechanism to determine whether or not a client is still connected to the daemon. This is the default. See the usage notes for other ways of simulating **keepalive**.

nokeepalive

Does not use the operating system's keep-alive mechanism to determine whether or not a client is still connected to the daemon.

routes

Specifies that a dual network exists and how public and private addresses are routed within a site. Select one of the below optionally followed by the **use** keyword and up to two interface names (i.e. *if1* and optionally *if2* immediately preceded by a comma; use **ifconfig** to display interfaces and their names):

split Two separate networks exist. Clients connecting with a private address can only be redirected to a server's private address. Clients

Configuration

connecting with a public address can only be redirected to a server's public address. If clients can use both types of addresses, *all* servers must be dual homed with a public *and* private address. Typically, you must specify the interfaces you are using.

- **common** Two common networks exist. Clients connecting with a private address are preferentially redirected to a server's private address but may be redirected to a server's public address if need be. However, clients connecting with a public address can only be redirected to a server's public address. All servers must have at least a public address. If the machine is dual-homed you must specify the interfaces you are using.
- **local** Two cross-routable networks exist. Clients connecting with a private address are preferentially redirected to a server's private address but may be redirected to a server's public address if need be. Clients connecting with a public address are preferentially redirected to a server's public address but may be redirected to a server's public address but may be redirected to a server's public address but may be redirected to a server's public address. If the machine is dual-homed it is advisable to specify the interfaces you are using for predictable access.

Warning, such a network configuration is not suitable for external access and a proxy server must be used for out of domain clients.

rpipa

Tries to resolve private IP addresses to host names. See the section on resolving private IP address for more information.

norpipa

Does not resolve private IP addresses to host names. This is the default.

tls Indicates that the specifications apply to the Transport Layer Security port.

Defaults

xrd.network cache 3h dnr norpipa

Notes

1) For systems that support **TCP** buffer auto-tuning as a *manual* option, specify a **buffsz** *blen* of 0 to turn on auto-tuning.

- 2) Setting the buffer size to a large value may cause the operating system's default value to be used. You should determine the maximum valid value for your system before specifying values greater that 64k.
- 3) Normally, the best performance is obtained by using **TCP** buffer autotuning.
- Even if you specific nodnr, domain Resolution may be forced on if you specify an allow directive using a host name or host name fragment or authorize file access via host names, netgroups, or domain names. Resolution is still optimized by caching the results for future use.
- 5) The daemon's internal timeout mechanism can be used to discover unconnected clients instead of **TCP keepalive** and may be more responsive. See the **timeout** directive. You should avoid using both mechanisms at the same time.
- 6) For aggressive keepalive processing you can use "kaparms 300,10,6".
- 7) By default, public-private networking support is disabled. You must specify the routes option to enable it. If you do specify for one server you must specify for all nodes in your cluster (i.e. servers and redirectors). Failure to do so may result in unreachable nodes..
- 8) If the supplied information is inconsistent with the server network settings, warning messages are printed and the public-private network support may be turned off for that server. You should verify that your specification is consistent with the server's networking configuration.
- 9) Interface names are arbitrary but usually are of the form enx, ethx, etc. One interface must be assigned a public address and the other the private address. This mechanism works best when all of the servers in a cluster use the same interface naming conventions; though the address assignments may differ. If this is not the case, you will need to use the ifelse-fi configuration syntax to special case particular nodes.
- 10) Dual public/private network are fully supported in Linux, MacOS, and in Solaris 11.
- 11) IP address caching is generally incompatible with a dynamic **DNS**. When **dyndns** is specified but no **cache** option has been specified, the cache timeout is set to zero. This effectively turns off IP address caching.

Example

```
xrd.network nokeepalive nodnr
xrd.network tls buffsz 512k
```

4.2.1 Dual Public/Private Network Guidelines

Before you configure a dual public/private network, determine if such a network is actually necessary. Administering dual networks is difficult and problem resolution rather onerous. Typical reasons and alternatives to running a dual network are:

- Conserving IPV4 addressees: consider using IPV6, which does not suffer from this problem.
- Performance: if private addresses are routed along with public addresses over the same networking hardware then the switch becomes the bottleneck and performance improvements are moot.
- Security: if you desire to restrict certain kinds of access you may be able to achieve the same result using router and switch settings (e.g. file walls, routing restrictions, etc) thus avoiding a dual network.

If you still wish to run a dual network, you should use the following guidelines to avoid access surprises and mysterious performance issues.

- Never register private addresses in a publicly accessible DNS server. This exposes your private network configuration and is considered bad practice. Private addresses should only be registered in a private DNS or zone registered to prevent external leakage.
- Never register a server's private and public address under a single host name unless both addresses have equal connectivity. While this practice works for simple applications, complex applications like **XRootD** and **Proof** attempt to use all addresses assigned to a particular host name. If connectivity is unequal, performance issues and connection failures are likely to occur.
- Never cluster servers with only a public address with servers that only have a private address if their name spaces overlap. While this may work for certain network routing topologies, it invariably introduces inconsistencies.
- Carefully review the **routes** option on the **xrd.network** directive to make sure your network routing topology and interfaces are correctly stated.

4.2.2 Resolving Private IP Addresses

By default, private **IP** addresses are not resolved to host names. This is commonly accepted practice to avoid **DNS** timeouts as private addresses are usually not registered in **DNS**. However, some installations may opt to register such addresses in either a private **DNS** or in a zoned public **DNS**. This actually may be necessary in cloud deployments where nodes within the cloud receive private addresses and a **NAT** box is installed to provide outside access. In such cases, there is usually a 1-to1 mapping between a public address (e.g. **IPv6**) to a corresponding private address (e.g. **IPv4**). The public address is registered in a public **DNS** while the private address is registered in a private **DNS** within the cloud. Both addresses are registered with the same host name. However, to avoid leaking private addresses you must specify the **xrd.network rpipa** option so that only host names are returned and not actual addresses. This allows clients on the public network to accesses nodes in the private network using the **NAT** box. Nodes in the private network also receive host names but since these names are registered within the private network, proper address resolution occurs.

4.2.3 Dynamic DNS

The **dyndns** option specifies that a Dynamic **DNS** is being used for the network. This is typically the case for containerized cloud deployments (private or public) managed by an orchestration scheme (e.g. Kubernetes). In such schemes, when a container starts with an arbitrary local IP address, its host name and address are entered into a local DNS. When the container stops, the entry is removed. Even on a container restart, the entry may be removed between the time the container stops and the time it restarts with a new IP address. This becomes a problem for servers expecting to contact specific services when those services have not yet been started or are being restarted. In the **XRootD** framework, cluster management services that supervisor and data servers rely on expect those services to be permanently registered in **DNS**; albeit with arbitrary non-permanent IP addresses.

The **dyndns** option notifies all nodes in an **XRootD** cluster using the network that **DNS** entries may come and go and resolution of IP addresses needs to be done at the time of contact not during initialization. Failure to specify the **dyndns** option when a Dynamic **DNS** is actually being used inevitably leads to random failures.

Of course, you may be able to avoid using a Dynamic **DNS** if you opt for host networking, at least for management services. However, many times that is not an option and when allowed severely limits orchestration choices.

4.3 pidpath

all.pidpath path

Function

Specify the location where the process id file (i.e. **pid** file) is to be written.

Parameters

path The path to be used to create the file where the daemon's process id is stored.

Defaults

The process id file is written into /tmp.

Notes

- If -n is specified on the command line, a subdirectory corresponding to the instance name (i.e., -n argument) is created in *path*, if one does not exist. This becomes the new *path*. This allows <u>fencing</u> multiple daemons running on the same node.
- 2) The **-s** command line option may be used to specify the path and filename to be used for the **pid** file.
- 3) The name of the **pid** file corresponds to the executable name suffixed by ".**pid**".

Example

all.pidpath /var/run/scalla

4.4 port

xrd.port [tls] {pnum | any} [if conds]

Function

Designate the port number to use for incoming requests.

Parameters

- **tls** Sets the preferred **TLS**-only (Transport Layer Security) port number. Otherwise, the default port number is set. See the usage notes on how the default is determined and the caveats when using the **tls** option.
- *pnum* The **TCP** port number or the **TCP** service name associated with a port in /etc/services file that the daemon should use for incoming requests. See the usage notes on how the default is determined.
- **any** Specifies that any available **TCP** port number may be used use for incoming requests. See the usage notes on how the default is determined.
- *conds* The conditions that must exist for this directive to apply. Refer to the description of the "**if**" directive on how to specify *conds*.

Defaults

See the usage notes.

Notes

- 1) The default port number is determined using the following rules:
 - The protocol specified port when the protocol is loaded.
 - The port specified on the protocol directive entry.
 - The port specified on the command line using **-p**.
 - Any available port number if **-p any** was specified on the command line.
 - The port associated with the service name that corresponds to the name of the program used to start the daemon (e.g., **xrootd**).
 - The port value of 1094.

- 2) The tls port number need only be specified if you wish to have a port that can *only* communicate using TLS at the outset. A client may discover this port using the kXR_query request with the tlsport as an argument. If not specified or used by a protocol, no TLS-only port is created.
- 3) Not all protocols support a TLS-only port. For instance, the xroot and xroots protocols negotiate TLS with the client and must first communicate without using TLS. So, TLS-only port cannot be used. The http protocol can use such a port but only for https connections. However, TLS-only port prevents it redirecting a TLS connection to a non-TLS connection.
- 4) When running clustered systems, you can keep a single configuration file that is applicable to all types of servers, as follows:
 - always specify "**xrd.port any**" in the configuration file, and
 - use the **if** modifier to identify the top-most servers (i.e., the initial point of contact also known as redirectors) and assign them fixed port numbers immediately following the "**xrd.port any**" directive.
- 4) Using the steps outlined above, the initial point of contact will have a wellknown port number. While all other servers will choose random port numbers, the ports are communicated to the cluster manager which then automatically manages the port numbers while redirecting clients.

Example

xrd.port xrdnew

4.5 protocol

xrd.protocol [tls] name[:port] {+port | {lib | *} [parms]}

Function

Configure a protocol that **xrd** is to use for incoming requests.

Parameters

tls Indicates that any connection to the port must communicate using TLS at the outset. Not all protocols support this option. See the notes for caveats.

name The name of the protocol you wish to configure.

- *port* The port number the protocol is to use for incoming requests. Specify a number, the name of a **TCP** service, or the word **any**. If *port* is not specified, the preferred port is used (see the **xrd.port** <u>directive</u>).
- +port Adds the specified *port* to the list of port number that the protocol may receive connections. The protocol name must have been previously defined. You may not omit the *port* specification when using this parameter. If the port already is associated with the protocol, only the **tls** designation is updated.
- *lib* The path to the shared library that contains the code the implements the protocol. If *lib* is an asterisk, the protocol refers to the built-in or the command line assigned protocol. Any pre-existing protocol definition with the same name is completely replaced by this definition.

parms Parameters to be passed to the protocol at load time.

Defaults

Not applicable.

Notes

1) The daemon expects that only one protocol is built-in. The name of this protocol must correspond to the name of the program implementing the daemon (e.g., **xrootd** implies **xroot** protocol). The built-in protocol may be overridden by the **-P** and **-L** command line options.

- 2) The built-in or assigned protocol is always loaded first followed by any additional protocols in the order they appear in the configuration file.
- 3) The tls option is meant to be used for protocols that require TLS but cannot configure it themselves. The xroot protocol is incompatible with this option as it negotiates the use of TLS using a non-TLS connection. The http protocol can work but only for https connections. However, enforcing TLS at the outset disables its ability to redirect a TLS connection to a non-TLS connection.
- 4) Most protocols can share the same port number because the framework picks the protocol that is compatible with the incoming data. For instance, the **xroot** and **http** protocols can both use the same port number. The framework automatically enables the **xroot** base port for **http** use. This makes it convenient in a clustered environment when an **http** connection is redirected to an **xroot** port number.
- 5) When the specified protocol name matches a previously declared protocol the *port, lib,* and *parms* specifications replace those in the previously specified directive. If the *port* is missing, the protocol uses its default port number. If the *parms* are missing then any existing *parms* are removed from the previous specification.
- 6) Additional protocols are dynamically loaded from the indicated *lib*.
- 7) A port of **any** assigns an arbitrary port number to the protocol.
- 8) Be aware that a protocol may choose its own port irrespective of what is actually specified. While current protocols respect the configured specification, future ones may not.
- 9) Only those protocols bound to a specific port are matched against incoming connections on that port. The daemon attempts to match each such protocol with an incoming connection on the associated port in the order that the protocols are specified. The built-in protocol is always tried first, if applicable.
- 10) Load-time parameters are specific to each protocol. Refer to the protocol requirements for details.
- 11) The **cms** and **xroot** protocols do not have any load-time parameters.
- 12) Up to eight different protocols may be specified. Each protocol may be assigned up to 8 different ports.

Example

```
xrd.protocol http:8000 libXrdHttp.so
xrd.protocol http:8080 +port
```

4.6 report

```
xrd.report dest1[,dest2] [every rsec] [-]option
option: all | buff | info | link | poll | process |
    prot[ocols] | sched | sgen | sync | syncwp
    [[-]option]
```

Function

Specify execution tracing options.

Parameters

- *dest1* is a *host:port* or a **UDP** named local socket where reports are to be sent. Reports are always sent as a single **UDP** message.
- *dest*2 is a secondary destination and must differ from *dest*1. The same report is delivered to *dest*2 and *dest*1.
- *rsec* determines how often reports are sent. Specify a number, optionally suffixed by **m** for **m**inutes, **s** for **s**econds (the default), or **h** for **h**ours. The default is every 10 minutes.
- *option* Specifies the reporting level. One or more options may be specified. The specifications are cumulative and processed left to right. Each option may be optionally prefixed by a minus sign to turn off the setting. The following options produce reports on:

all	selects all possible reports
buff	I/O buffer activity
link	connection and socket I/O activity
poll	socket activity other than I/O
process	process resources
protocols	protocol specific information
sched	scheduling and thread activity
sgen	statistics generation
sync	synchronizes data for completeness (see the notes)
syncwp	synchronizes data only when practically possible

Defaults

Reporting is disabled.

Notes

- Report messages are encoded in XML format. Refer to the xrootd protocol specification on the actual format and embedded information; as described under the response format for the kXR_QStats option of the kXR_query request.
- By default, statistical values are obtained without data access synchronization. This may occasionally produce incomplete or inaccurate values. However, because information is collected asynchronously this has little impact on the server.
- 3) If absolute accuracy is required, you should specify the **sync** option. Be aware that reporting may require a significant amount of elapsed time while the server synchronizes its activities in order to produce accurate and consistent data.
- 4) If absolute accuracy is desired but not required, you should specify the syncwp option. The server synchronizes its activities only when possible. If the server is too active, an asynchronous report is done. The sgen report segment provides information on whether the report was synchronous or not and how much time it took to generate.
- 5) For scalability reasons, you should feed all **UDP** messages to one or more collectors whose sole function is to multiplex the **UDP** message streams into a single buffered serial stream. Generally, attempting to do more in a **UDP** message receiver substantially increases the chance for lost **UDP** messages.
- 6) A **UDP** message multiplexor and **XML** parser, **mpxstats**, is available as part of the reference **XRootD** distribution. Refer to the "Monitoring" reference for details.

Example

xrd.report myhost:1234 every 15m all -poll

4.7 sched

```
xrd.sched parms
parms: [avlt avlt] [core {asis | max | off}]
[idle idle] [maxt maxt] [mint mint] [stksz size]
```

Function

Specify when threads are created, how many can be created, and when they should be destroyed.

Parameters

avlt avlt

The number of threads that must always be available to service a request. These threads are never bound to any connection. Excess threads above this quantity will be allowed to bind with a socket until either the socket becomes idle or the number of available threads falls under *avlt*. The default is one half of the *mint* value.

core {assis | max | off}

Sets	the	limit	for	core	file	pro	duct	tion.	Choices are	
		-	-					-		

- **assis** leave the current setting alone.
- **max** allow core files up the hard limit maximum (the default).
- off turn off core file production.

idle idle

The interval between checks for underused threads. Underused threads in excess of the *mint* value are terminated. Specify a number, optionally suffixed by **m** for **m**inutes, **s** for **s**econds (the default), or **h** for **h**ours. The default is every 13 minutes (i.e., 13m). Specifying a value of zero prevents threads from being terminated even if they are idle.

maxt maxt

The maximum number of threads that may be created to service requests. The number of threads will dynamically vary between *mint* and *maxt*.

mint mint

The minimum number of threads that must exist to handle requests. Once this number has been created, it is never reduced.

stksz size

The default thread stack size. Specify the number of bytes, optionally suffixed by **k** for **k**ilobytes or **m** for **m**egabytes. The default is controlled by the target operating system.

Defaults

xrd.sched mint 8 maxt 2048 avlt 512 idle 780

Notes

- 1) The *mint*-number of threads are eventually created.
- 2) The stack size is controlled by the target operating system used to create xrootd. For instance, in Solaris when sizeof(long) is 4 (indicating a 32-bit architecture), a 1M stack size is used. When sizeof(long) is 8 (indicating a 64-bit architecture or an LP64 data model) a 2M stack size is used. In Linux, the stack grows, as needed, to a maximum of 2M.
- 3) You should periodically review whether or not you have sufficient number of threads. The daemon prints a warning message the first time the *maxt* value is reached and more threads are needed.
- 4) If the daemon indicates that the thread limit was reached but less than *maxt* threads were created; then the target operating system maximum has been reached. This now becomes the new *maxt* value.
- 5) *Warning*, you should not change the thread parameters unless there is an overpowering reason to do so. The system is optimized for having many thread readily available. Constraining the number of threads may yield random failures that are hard to explain.

Example

xrd.sched mint 10 maxt 100 avlt 20

4.8 sitename

all.sitename sname

Function

Specify the site name to be included in monitoring records.

Parameters

sname

The 1- to 63-character name of the site. The name may include letters, digits, and the symbols "_-:.". Other symbols are converted to a period. If the name is longer than 63 characters it is truncated to 63 characters.

Defaults

None.

Notes

- 1) The **-S** command line option overrides the **sitename** directive.
- 2) The first **sitename** directive takes precedence over any subsequent **sitename** directives.

Example

all.sitename slac

4.9 tcpmonlib

xrd.tcpmonlib [++] path [parms]

Function

Specify the location of the **TCP** connection statistics monitoring plug-in.

Parameters

++ The specified plug-in should stack on top of the existing plug-in or default. A stacked plug-in cannot be overridden by a subsequent directive.

path The absolute path to the shared library that contains an implementation of the **TCP** connection statistics monitor.

parms Optional parameters to be passed to the plug-in object creation function.

Defaults

None.

Notes

- The TCP connection monitor plug-in interface is defined in the XrdTcpMonPin.hh include file. Refer to this file on how to create a custom monitoring plug-in.
- 2) You must specify the **tcpmon** option in the **xrootd.monitor** directive in order to enable the **TCP** connection monitoring.
- 3) The plug-in is called just before the TCP socket to a client is closed.

Example

ofs.authlib /opt/xrootd/lib/libAuth.so

4.10 timeout

```
xrd.timeout parms
parms: [hail hlto[h | m | s]] [idle idto[h | m | s]]
[kill klto[h | m | s]] [read rdto[h | m | s]]
```

Function

Specify timeout parameters.

Parameters

hail hlto

The maximum number of seconds to wait for data to arrive after a connection is accepted. Specify a number optionally suffixed by **h** for hours, **m** for minutes, or **s** for seconds, the default.

idle idto

The number of seconds a connection may remain idle before it is closed. Specify a number optionally suffixed by **h** for hours, **m** for minutes, or **s** for seconds, the default. A value of 0 disables idle timeout processing.

kill klto

The number of seconds to wait for an "end session" request to complete. Specify a number optionally suffixed by **h** for hours, **m** for minutes, or **s** for seconds, the default.

read rdto

The number of seconds a read may wait for data before it is either terminated or rescheduled. Specify a number optionally suffixed by **h** for hours, **m** for minutes, or **s** for seconds, the default.

Defaults

xrd.timeout hail 30 idle 0 kill 3 read 5

Notes

- 1) The **idle** timeout prevents accumulation of dead connections which may happen when a client host machine crashes.
- 2) Currently, **idle** timeouts are disabled. You may enable them by specifying an *idto* value greater than zero.
- 3) Forced closure of connections is safe if the protocol supports dynamic reconnection, as the **xroot** protocol does.
- 4) The **read** timeout forces a link to be closed should the initial protocol identification data not arrive within the timeout interval. After which, connections that do not send all of their data in the indicated period are simply rescheduled to the background.
- 5) Avoid setting short idle timeouts (e.g. less than 2 minutes). The framework oversamples timeout conditions so that it can accurately meet the specified value. Shorter timeouts require a higher sampling rate which increases overhead.

Example

xrd.timeout idle 120m read 10

4.11 tlsciphers

xrd.tlsciphers ciphers

Function

Specify the allowed ciphers for transport layer security (TLS).

Parameters

ciphers

A list of colon separated ciphers that are allowed to be used.

Defaults

For **OpenSSL** versions greater than 1.0.2 the ciphers recommended by mozilla.org version 5.4 guidelines are used. These are strict ciphers. For older **OpenSSL** versions, generic ciphers are used for compatibility reasons.

Notes

1) The **tls.ciphers** directive is provided in cases where a default cipher has been shown to be insecure and should be removed. In this case, you need to specify all of the ciphers less the one you wish to eliminate.

Example

xrd.tlsciphers ALL:!LOW:!EXP:!MD5:!MD2

4.12 trace

Function

Specify execution tracing options.

Parameters

<i>option</i> Specifies the tracing level. One or more options may be specified. The
specifications are cumulative and processed left to right. Each option may be
optionally prefixed by a minus sign to turn off the setting. Valid options are:

all	selects all possible trace levels
conn	traces connection activity
debug	traces internal activities for debugging purposes
mem	traces memory management functions
net	traces network management functions
none	traces nothing
off	a synonym for NONE
poll	traces I/O interrupt polling activities
protocol	traces protocol activity (see the notes)
sched	traces scheduling functions
tls	a synonym for the combination tlsctx and tlssok
tlxctx	traces TLS context activities
tlsio	traces TLS I/O activities
tlssok	traces TLS socket activities

Defaults

Tracing is disabled.

Notes

- 1) All tracing is forcibly enabled when the daemon is invoked with the **-d** option.
- 2) All previous trace settings are discarded when **none** or **off** is encountered.
- 3) The **protocol** trace option is passed along to the all loaded protocols that may or may not respect the option or may have their own options.

Example

xrd.trace all -debug

5 xrootd Directives by Category

5.1 Data Access

all.export	Specify the file system paths that may be accessed.
xrootd.fslib	Specify the file system plug-in to be used for data access.
xrootd.redirect	Specify client redirection by type of request, access path, and
	possible errors during access.

5.2 Data Integrity

xrootd.chksum Enable file checksum calculation.

5.3 Debugging

xrootd.diglib	Enable interactive remote debugging.
xrootd.trace	Specify execution tracing options.

5.4 Monitoring

xrootd.mongstreamSpecify custom g-stream parameters.xrootd.monitorSpecify which statistics are to be collected and where they are to be sent.

5.5 Prepare Processing

xrootd.prep Specify how prepare requests tracking should be handled.

5.6 Security

xrootd.seclib	Specify the location of the security interface layer.
xrootd.log	Specify which events are to be logged.
xrootd.tls	Specify TLS requirements by request category.

5.7 Tuning

xrootd.async	Specify asynchronous data processing features and limits.
xrootd.fsoverload	Specify how file system overloads are to be handled.
xrootd.tlsreuse	Specify TLS session cache characteristics.

6 Common xrootd Configuration Directives

6.1 export

all.export {path | *[?]} [[no]lock] [oss options]

Function

Specify a valid path prefix for file requests.

Parameters

- *path* An absolute path prefix for valid file requests. Only files starting with this prefix are allowed in requests.
- * Allow arbitrary object identifiers (i.e. names that do not start with a slash). The names are not inspected in any way and passed as is to the file system plug-in.
- *? Allow arbitrary object identifiers (i.e. names that do not start with a slash). Inspected the names for CGI information and, if present, separate it from the object identifier (i.e. characters before the question mark) before passing the object name and CGI information to the file system plug-in.
- **lock** Uses standard xroot protection against multiple writers. This is the default.

nolock

Does not protect against multiple writers.

oss_options

Optional **oss** options that affect how the path is processed by the storage system and cluster service. Refer to the "Open File System & Open Storage System Configuration Reference" and the "Clustering Configuration Reference".

Defaults

xrootd.export /tmp lock

Notes

- 1) For security purposes, only files in /**tmp** are allowed to be accessed unless you specify otherwise. You may specify valid paths either on the command line or using the **export** configuration directive.
- 2) Do *not* prefix *path* with the **oss localroot** directive path, if any.
- 3) By default, a file may be opened by a single writer with no readers or multiple readers without any writer. If an external locking mechanism is used or no locking mechanism is needed; specify the **nolock** option to disable the default.
- 4) The **[no]lock** option *must* appear *before* any **oss** options.
- 5) The underlying file system plug-in as well as the storage system plug-in must support object identifiers in order to use the * or *? export. The default file system plug-in will pass the object identifier to the storage system plug-in for the common set of file operations. However, the default storage system plug-in will not load if object identifiers are being exported.
- 6) Object identifiers exportation is meant to support object store plug-ins such as the **Ceph** block storage plug-in.

Example

xrootd.export /store

6.2 seclib

xrootd.seclib {default | path}

Function

Specify the location of the security interface layer.

Parameters

default

Uses the default security plug-in the security interface.

path The absolute path to the shared library that contains an implementation of the <u>Sec</u>urity (sec) interface that xrootd is to use for strong authentication(e.g., Kerberos, GSI, etc).

Defaults

Strong authentication is disabled unless **seclib** is specified.

Notes

- 1) The **sec** interface allows you to provide an arbitrary authentication implementation (e.g., **Kerberos**, **GSI**, etc).
- 2) A **sec** implementation requires that compatible interface libraries be used on the server and client sides of the connection.
- 3) Refer to **XrdSecEntity.hh** and **XrdSecInterface.h**h for guideline on how to write a **sec** interface.
- 4) It is up to the **sfs** implementation to use authentication information to restrict access to files.
- 5) The provided **ofs** implementation can use authentication information for access control purposes.
- 6) The default **sfs** implementation does not provide any access control.

Example

xrootd.seclib /opt/xrootd/lib/libosec.so

7 Esoteric xrootd Configuration Directives

7.1 async

```
xrootd.async parms
parms: [force] [limit clim] [maxsegs smax]
    [maxstalls mstall] [maxtot slim]
    [minsz reqsz[k | m | g]] [minsfsz sfsz[k | m | g]]
    [off] [nosf] [segsize segsz[k | m | g]] [syncw]
```

Function

Specify how asynchronous I/O is to be handled.

Parameters

force Uses asynchronous I/O for all requests, even if the client did not ask for asynchronous handling.

limit clim

The maximum allowed number of outstanding asynchronous requests per client connection. Any additional requests past *clim* are synchronously handled. The default is eight (8).

maxsegs smax

The maximum number of simultaneous asynchronous operations that may any one request may have in progress. The default is eight (8).

maxstalls *mstall*

The maximum number of times a client may fail to deliver data at a sufficient rate to keep up with asynchronous I/O needs before future requests from the client are synchronously handled. Asynchronous handling is tried again after *mstall* number of synchronously handled requests. The default is eight (8).

maxtot slim

The maximum number of simultaneous asynchronous operations the server may have in progress. The default is 4,096.

minsz reqsz

The minimum number of bytes that must be read or written in a single client request for that request to be asynchronously handled. I/O requests smaller than *reqsz* are always synchronously handled. The *reqsz* can be suffixed by **k**, **m**, or **g** to indicate **k**ilo-, **m**ega-, or **g**iga-bytes; respectively. The default is one half of the initial *segsz*.

minsfsz sfsz

The minimum number of bytes that must be read in a single client request for that request to be handled using sendfile(). I/O requests smaller than *sfsz* are always handled in the standard way. The *sfsz* can be suffixed by **k**, **m**, or **g** to indicate **k**ilo-, **m**ega-, or **g**iga-bytes; respectively. The default 8192 for Linux, 1 otherwise.

off Disables asynchronous I/O for all requests.

nosf Disables using sendfile(), where available, for all read requests.

segsize segsz

The ideal asynchronous I/O segment size. The server attempts to quantize asynchronous I/O request into *segsz* pices. The *segsz* can be suffixed by \mathbf{k} , \mathbf{m} , or \mathbf{g} to indicate \mathbf{k} ilo-, \mathbf{m} ega-, or \mathbf{g} iga-bytes; respectively. The default is 64k. See the usage notes on how the system dynamically adjusts this value.

syncw

Uses synchronous I/O for all **fsync** requests. Otherwise, asynchronous I/O is used for **fsync** requests if the client requested asynchronous I/O or if the **force** has been specified.

Defaults

xrootd.async limit 8 maxsegs 8 maxstalls 5 maxtot 4096 segsz 64k

Notes

- Asynchronous requests allow the client to start a number of read operations at one time and wait for the request to complete in optimal order. When properly employed, asynchronous requests may substantially improve overall client processing speed.
- Asynchronous processing represents a substantial resource commitment on part of the daemon. Each operation requires the dispatching of a separate thread. Rampant asynchronous processing may exhaust resource limits. Use the **maxpl** and **maxps** values to limit the amount of asynchronous processing.
- 3) Asynchronous processing is effective when the disk transfer rate approaches the network transfer rate. Thus, asynchronous processing is enabled only when a sufficiently large amount of data is requested by the client at one time. Use the **minsz** parameter to control the point where asynchronous operation is effective.
- 4) The segsz parameter specifies the ideal i/o size for asynchronous operations in order to maintain continuous disk/network transfer overlap. Requests are broken into segsz units. If the requested size is smaller than segsz, the server will use half the segsz. If the number of units is more than twice maxsegs, the server will use twice the segsz.
- 5) Conversion of asynchronous requests to synchronous requests is transparent to the client.
- 6) The sendfile() interface allows data to be transferred directly from the kernel's file system memory cache to a client. Generally, this significantly reduced system overhead. The sendfile() function is available in Solaris 5.8 and above, as well as Linux 2.6 and above.
- 7) Use the **nosf** option in cases where you suspect that the sendfile() interface is causing data transfer problems.

Example

xrootd.async minsz 1M

7.2 chksum

xrootd.chksum [chkcgi] [max num] digest [path [args]]

```
digest: algorithim [digest]
```

Function

Specify how file check sums are computed.

Parameters

chkcgi

Always checks the **cgi** information, if any, for the **cks.type** element that can be used to select a checksum algorithm. The **cgi** information is not checked if only one digest is specified for backward compatibility. It is always checked if more than one digest is specified, making **chkcgi** unnecessary. See the usage notes for more information.

num Maximum number of checksum calculations that may run at the same time. Specifying 0 prevents real-time check summing. See the notes for more information.

algorithm

The name of the checksum digest (e.g., md5) used for the check summing. Specify one or more supported digests, each separated by a space. The first algorithm becomes the default algorithm. See the usage notes on how multiple digests are supported,

- *path* The absolute path of the program that computes the check sum. If *path* is not specified, checksums are internally performed.
- *args* Initial arguments to be passed to the program identified by *path*, if any.

Defaults

The default **max** is 4; otherwise. If *path* is not specified, checksums are internally performed. File check summing is not supported unless the directive is specified.

Notes

- 1) When a client issues an **xrootd** query checksum request, the following steps are performed:
 - a. A checksum digest is selected as follows:
 - i. If a single algorithm is specified and **chkcgi** was not specified, the digest in the configuration file is used.
 - ii. If a single algorithm is specified and **chkgi** is specified, a **cgi** scan is made for **cks.type** and, if specified, its argument must match the single algorithm in the configuration file or an error results. In any case, the digest in the configuration file is used.
 - iii. If more than one algorithm has been specified, a cgi scan is made for cks.type and, if specified, its argument must match one of the specified algorithms in the configuration file or an error results. If there is a match, the cks.type argument is used as the desired digest. If cks.type is not found, then the first algorithm specified in the configuration file is used.
 - b. A check is made that the client has lookup privileges for the file and that a valid checksum has been recorded for the file. If both are true, that checksum is sent back to the client. If the client lacks lookup privileges, an access error is sent back to the client.
 - c. Since a checksum needs to be computed the **max** value applies. If it is zero, the client is told that the checksum is not available.
 - d. If the checksum is natively supported and no program path has been specified, a new checksum is locally computed and recorded for future queries. Otherwise, the program named in path is executed to compute a new checksum and it is not recorded for future queries. Of course, the program may record the checksum in some way for future queries.
 - e. Either the previously recorded checksum or the computed checksum is provided to the client.
- 2) Native checksums are **adler32**, **crc32**, and **md5**.
- 3) Use the **ofs.ckslib** directive to add new digests or improve the performance of the native digests.
- 4) Since computation of multiple checksums is CPU and memory intensive choose the **max** with circumspection. You can control memory usage via the **ofs.cksrdsz** directive.
- 5) The **ofs** directives are documented on the OFS/OSS reference manual.
- 6) When the program identified by *path* is invoked, it is passed the path to the file that is to be processed. The actual argument list varies depending on whether or not a single algorithm has been specified, as follows:

- a. When a single algorithm has been specified, the program is passed the file path as the last argument and is the only argument if no *args* have been specified.
- b. When multiple algorithms have been specified, the program is passed the file path as the last argument and the checksum algorithm name as the second to the last argument. If no *args* have been specified, these are the only two arguments that are passed.
- 7) The program must output on standard out a single checksum value; normally ending with a new-line ('\n') character and terminate with a status code of zero. If the program terminates with a non-zero status code or returns no output, the client's request fails.
- 8) Upon success, the returned checksum value is passed back to the client, prefixed by the digest token, *digest*.
- 9) *Warning*: If an external checksum program is specified (i.e. *path* is specified), then neither the **oss.localroot** nor **oss.namelib** directives are applied to the logical file name before passing the file name to the specified program that computes the checksum. Hence, the program is responsible for converting a logical file name to a physical file name.
- 10) When checksums are natively computed (i.e., path is not specified), then the **oss.localroot** and **oss.namelib** directives are applied to the logical file name. The checksum is computed against the resulting physical file name.
- 11) The **chkcgi** option is provided for backward compatibility. In previous releases only one algorithm could be specified and **cgi** information was immaterial. This processing mode remains the default when only a single algorithm is specified. You may wish to verify that a client as not requesting an unsupported digest in the case where some servers support multiple checksums and others do not.
- 12) The administrator's interface allows you to list and cancel checksum jobs. This applies to external as well as internal computation of the checksum.
- 13) When max is zero, checksums on demand are prohibited. This requires that checksums to be pre-computed. This can be done using the frm_admin chksum command. See the File Residency Manager reference.
- 14) Using an external checksum calculation via the path option disables the server's ability to return checksums in a directory listing.

Example

xrootd.chksum max 2 md5

7.3 diglib

xrootd.diglib * authpath

Function

Enable remote debugging via the **digFS** read-only file system.

Parameters

* Loads the built-in version of **digFS**; the only the version currently supported.

authpath

The path to the authorization file that describes who is allowed to access **digFS** and what kind of information they may view.

Defaults

By default, **digFS** is disabled.

Notes

- 1) The **digFS** provides a virtual read-only file system view of key information about **xrootd** and **cmsd** that is valuable to remotely debug system problems.
- 2) Since **digFS** exposes system information an authorization file describing access permissions is required. See the next section.
- 3) When **diglib** is specified, the /=/ directory is automatically exported and available to authorized users. You *must not* list /=/ in the **all.export** list.
- 4) The /=/ path always refers to local storage regardless of server role and is never subject to redirection.
- 5) Only **close**, **dirlist**, **locate**, **open**, **read**, and **stat** requests can be vectored to **digFS**. Other requests referring to /=/ are disallowed.
- 6) The **digFS** accepts configuration directives starting with **dig**. Refer to subsequent sections for a description of these directives.

Example

```
xrootd.diglib * /etc/xrootd/digauth.cf
```

7.3.1 Authorizing digFS Access

The file describing **digFS** access permissions is composed of newline delimited records. Each record describes a single entity that is authorized to access certain information. The format of each record is

```
info allow aprot ident
info: all | [-]conf | [-]core | [-]logs | [-]proc | [info]
aprot: gsi | host | krb5 | pwd | sss | unix
ident: g=group | h=host | n=name | o=org | r=role | [ident]
```

Parameters

info Authorizes the entity described in the record to access certain information. Use the word **all** to allow access to all information. If you specify **all**, you can remove specific information by specifying subsequent information keywords prefixed by a minus sign. Alternatively, list the *info* keywords to enable access to the associated information described below.

Keyword	Information	Keyword	Information
conf	configuration file	logs	log files
core	core files	proc	process information (Linux only)

aprot Specifies the authentication protocol that must be used in order to use **digFS**. Only one protocol per entity description may be specified. Since the information provided by **digFS** is sensitive in nature you should use the strongest authentication protocol consistent with site policies. The following table lists the default protocols¹ from strongest to weakest. Additionally, the rightmost column lists the *ident* tags that can be successfully specified relative to that protocol since not every protocol identifies clients in the same way. See the **XRootD** security reference for more detailed information.

¹ Authentication is plug-in based and any implemented authentication protocol may be specified as *aprot*.

Protocol	Descritption	Meaningful ident Codes
krb5	Kerberos Version 5	h n
gsi	Grid Security Infrastructure (i.e. x.509)	g h n o r
SSS	Simple Shared Secret	g h n
pwd	Password	g h n o r
host	DNS resolved hostname	h
unix	NFS V2-Style authentication	g h n

ident Authorizes the *aprot* authenticated entity possessing the specified identity values access to info **digFS** information. Identity values are specified as key value pairs. The entity must match all the specified pairs in order to be granted access. An imbedded space in a value must be designated as a \s (i.e. two character sequence). Specifying an inappropriate key relative to an authentication protocol prohibits access. The following table describes the possible key value pairs.

Key	Value
g	Group name
h	Fully qualified hostname
n	Authentication-specific protocol client identity string (see notes)
0	Organization name
r	Role name

Notes

- 1) Valid entries in the *authfile* are used and syntactically incorrect entries are discarded. At least one valid entry must exist for **digFS** to be enabled.
- 2) If the modification time of the *authfile* changes outside of a 5 second window it is reprocessed. This allows you to modify the *authfile* on a running system. However, you must atomically update the file as follows:
 - a. Create a copy of the file.
 - b. Modify the copy as needed.
 - c. Rename the copy to be the original name (i.e. use mv).

Distributing a modified copy of the file to other hosts should also use rename to install the new *authfile*.

- 3) Each authentication protocol has a specific way of identifying a client. For instance, x.509 (i.e. **gsi**) uses distinguished name (i.e. dn). Depending on the security configuration the protocol-specific name may be mapped to a Unix name. If so, you must use the mapped name not the original name.
- If an entity is associated with more than one group name then the specified group (i.e. g=) must match one of the associated group names.
- 5) Starting in version 4.2 you are able to enable **digFS** but prevent its use by simply not creating an authorization file or commenting out all authorization entries. This allows you to enable its use in real-time without restarting **XRootD** by either creating an authorization file or adding authorization lines to an existing file.
- 6) Prior to 4.2 you must have a valid authorization file with at least one authorization entry. However, that entry may be unsatisfiable. This also allows you to selective enable or disable **digFS** without an **XRootD** restart.

Example

```
all -core allow krb5 h=test.org n=xtestor
conf logs allow gsi g=atlas n=theuser
```

7.3.2 Optional digFS Directives

The **digFS** accepts the following directives in the configuration file.

7.3.2.1 addconf

dig.addconf path [fname]

Function

Add a configuration file reference to the **digFS** namespace.

Parameters

path The absolute path to a regular file that is to be added to "/=/conf/etc". The name of the file will be the same as the last component of path unless *fname* is specified.

fname The name that is to appear in "/=/conf/etc" but refers to path.

Defaults

None.

Notes

- 1) The *path* is only added if it is readable by the **xrootd** server.
- 2) This directive allows you to make other server related configuration files available via **digFS**.

Example

dig.addconf /etc/sysconfig/xrootd

7.3.2.2 log

```
dig.log parm [ parm ]
parm: deny | grant | none
```

Function

Control the level of logging.

Parameters

parm The level of logging; specify one or more of:

- **deny** log file access denials **grant** - log file access approvals
- **none** turn off logging

Defaults

dig.log deny grant

Notes

1) To enable logging of denials and approvals you must specify both **deny** and **grant** parameters.

Example

dig.log deny

7.3.3 Using digFS

The **digFS** file system can be accessed using standard file system applications. All information is rooted in the /=/ directory and follows a standard layout. The following table describes directory tree.

Directory	Subdirectory	Contents	
/=/conf		Configuration files cmsd.cf and xrootd.cf	
	/etc	Other site selected configuration files.	
/=/core		Core files	
	/cmsd	Directory holding cmsd core files.	
	/xrootd	Directory holding xrootd core files.	
/=/logs		Log files	
	/cmsd	Directory holding cmsd log files.	
	/xrootd	Directory holding xrootd log files.	
/=/proc		/proc files (Linux only)	
	/cmsd	Directory holding the cmsd proc files.	
	/xrootd	Directory holding the xrootd proc files.	

If the **cmsd** and the **xrootd** share the same configuration file the **/=/conf/cmsd.cf** and **/=/conf/xrootd.cf** will be identical. If they share the core file directory or the log file directory; the same files may appear in the **cmsd** and **xrootd** subdirectories. As other components are added to **digFS**, additional executable names may appear in each root subdirectory.

To find out your access rights, simply list the entries in the /=/ directory. Only the subdirectories for which you are authorized are displayed.

7.4 fslib

```
xrootd.fslib [++] [throttle | path]
```

```
Deprecated (see notes):
```

```
xrootd.fslib [throttle | path2] {default | path1}
```

Function

Specify the location of the file system interface layer.

Parameters

++ The specified plug-in should stack on top of the existing plug-in or default. Once specified, it cannot be replaced by a subsequent directive.

throttle

Loads libXrdThrottle.so to wrap the subsequent library specification.

- *path* The path to the shared library that contains the file system plug-in.
- *path2* The path to the shared library that is to be used as the wrapper for the subsequent library specification.

default

Loads a built-in version of the file system implementation.

path1 The path to the shared library that contains an implementation of the <u>Open</u> <u>File System</u> (ofs) interface that xrootd is to use for file system specific operations (e.g., open, close, read, write, rename, etc).

Defaults

xrootd.fslib default

Notes

 When you only specify the shared library filename, the library is located using the standard platform-dependent loader rules (e.g. well know places followed by the LD_LIBRARY_PATH envar setting).

- 2) The **sfs** interface allows you to provide an arbitrary file system implementation. It is documented in **XrdSfsInterface.hh**. Refer to this include file for differences between version 1 and 2 instantiation.
- 3) The deprecated version of his directive should be avoided The general version is a superset of the deprecated version. In the common case

ofs.fslib throttle default

can be simply replaced by

ofs.fslib ++ throttle

Should you mix both styles, the deprecated version is handled before the general version of the directive which may be confusing.

Example

xrootd.fslib /opt/xrootd/lib/libofs.so

7.5 fsoverload

```
xrootd.fsoverload [[no]bypass] [redirect target]
        [stall sec]
target: host:port[%host:port]
host: dnsname | [ipv6addr] | ipv4addr
```

Function

Specify how to handle file system overload.

Parameters

[no]bypass

Specifies whether or not clients should be redirected to the client-specified forwarding destination when the file system indicates it is overloaded. This option is only meaningful for servers configured as forwarding proxies and is ignored if that is not the case. It is only applicable when the client specifies a forwarding destination.

redirect target

The name or address of the *host* and *port* number where clients are to be redirected when the file system indicates that it is overloaded. The target consists of one or two *host:port* specifications with the second separated by a percent sign (%). When a second *host:port* is specified, then clients connecting using a private IP address are redirected to the second *host:port* while clients connecting with a public IP address are redirected to the first *host:port*. If only one *host:port* is specified, all clients are redirected to that host.

stall sec

Specifies how long the client should be stalled when a redirect target is not available and the file system indicates that it is overloaded. After the stall, clients will re-issue the request. A value of zero passes back an overload error to the client when the file system indicates an overload.

Defaults

xrootd.fsoverload nobypass stall 33

Notes

- 1) The **fsoverload** directive is most effective for disk caching proxy servers. Refer to the "Proxy Storage Services Configuration Reference" for additional information on how to effectively use this directive.
- 2) Currently, the **fsoverload** directive only applies to file open requests. All other requests encountering a file system overload event fail with an overload error.
- 3) The **bypass** directive only applies to release 4.0 or higher clients. Older clients that specify a forwarding path are subject to the **stall** option should a file system overload event occur.

Example

xrootd.fsoverload bypass redirect foo.proxy.edu:1094

7.6 log

```
xrootd.log [-]levent [ [-]levent ] [• • •]
```

```
levent: all | disc | login
```

Function

Specify event logging options.

Parameters

levent Specifies the events to be logged level. One ore more events may be specified. The specifications are cumulative and processed left to right. Each event may be optionally prefixed by a minus sign to turn off the setting. Valid events are:

all	logs all possible events, the default
disc	disconnect events
login	login events

Defaults

xrootd.log all

Notes

1) Events messages are routed to the **xrootd** log file.

Example

xrootd.log all -login

7.7 mongstream

```
xrootd.mongstream events use parms
events: {all | ccm | pfc | tcpmon} [events]
parms: [flush intvl[m|s|h]] [maxlen size[k]]
[send fmt [noident] host:port]
fmt: {cgi | json} [hdr] | nohdr
hdr: dflthdr | sitehdr | hosthdr | insthdr | fullhdr
```

Function

Specify g-stream monitoring parameters and, optionally, enable selected events.

Parameters

events The events to which this directive applies. The permissible events are:

Event	Explanation
all	Selection applies to all of the events below.
ccm	cache context management information.
pfc	proxy file cache information (i.e. proxy disk caching).
tcpmon	TCP connection statistics at time of socket close.

flush intvl

The maximum time event data may be internally buffered before it is sent to the monitoring destination. Specify a number optionally suffixed by **h** for hours, **m** for minutes, or **s** for seconds, the default. The default comes from the **xrootd.monitor** <u>directive</u>.

maxlen *size*

the maximum size of the datagram. Specify no less than 1024 and no more than 64k. The *size* can be suffixed by \mathbf{k} to indicate \mathbf{k} ilo-bytes. The default comes from the **xrootd.monitor** <u>directive</u>.

send fmt [noident] host:port

specifies header formatting and the destination for the selected g-stream events. This overrides whatever is specified in the **xrootd.monitor** <u>directive</u>

dest option. The *fmt* parameter specifies the header format, if any:

- cgi formats the header as a CGI query string
- **json** formats the header as a **JSON** object

nohdr do not include any header for any message. See the notes for caveats.

When an actual format (i.e. not **nohdr**) is specified, you may specify the kind of header to be used:

dflthdr uses a minimal header to identify the message and timing.

sitehdr uses dflthdr but adds the site name, if any.

hosthdr uses sitehdr but adds the host name.

insthdr uses **hosthdr** but adds the port and instance name.

fullhdr uses insthdr but adds the program name and version.

When the previous specification is followed by **noident**, the server does not send periodic identification messages. The **noident** option is the default when **nohdr** is specified since an identification record requires a header.

The final element is the endpoint specification. Specify the *host* and *port* where the selected g-stream messages are to be sent using **UDP**.

Defaults

Defaults come from the **xrootd.monior** directive. If a header format is specified, the default is **dflthdr**.

Notes

- The mongstream directive is meant to customize specific g-stream events. It also allows enabling these events without enabling common monitoring using the xrootd.monitor directive.
- 2) If you do not specify the **send** parameter, then g-stream monitoring is controlled by the **xrootd.monitor dest** parameter. Otherwise, the **send** specification overrides the **xrootd.monitor** specification.
- You may still use common monitoring for g-streams via the xrootd.monitor directive yet select specific flush intervals and message sizes using the mongstream directive by simply not specifying the send parameter.

- 4) Specifying **nohdr** automatically disables identification messages as well as any map messages. The latter makes dictionary mapping inoperative. If a g-stream plug-in uses dictionary mapping, that mapping is never recorded.
- 5) Unless the monitoring collectors are able to handle multiple header formats, it is unwise to send different header formats to the same collector. This is not enforced.
- 6) The **mongstream** directive is cumulative with each subsequent directive replacing previously set values.

Example

xrootd.mongstream all use send json datacoll:1234

7.8 monitor

```
xrootd.monitor [...] [options] [dest dest [dest dest ]]
options: [all] [auth] [flush [io] intvl[m|s|h]]
    [fstat intvl[m|s|h] [lfn] [ops] [ssq] [xfr cnt]]
    [ident {intvl[m|s|h] | off}] [fbuff size[k]]
    [gbuff size[k]] [mbuff size[k]] [rbuff size[k]]
    [rnums cnt] [window intvl[m|s|h]]
dest: [events] host:port
events: {ccm | files | fstat | io | info | pfc | redir |
    tcpmon | user} [events]
```

Function

Specify monitoring parameters and, optionally, enable it.

Parameters

•••	uses previousl	y set values	s to allow a contin	nuation. If th	he directive doe	es not
	start with a tri	ple dot, all	previous values a	are reset to i	nitial defaults.	

- **all** Automatically enables monitoring for all connections. If **all** is not specified, monitoring is only enabled upon client request for that specific client.
- **auth** includes authentication information along with user information, when **user** is specified and authentication has been configured.

flush [io] intvl

The maximum time event data may be internally buffered before it is sent to the monitoring destination. Specify a number optionally suffixed by **h** for hours, **m** for minutes, or **s** for seconds, the default. When **io** is specified, io event data is also subject to flushing. Otherwise, only non-io events are flushed. The default only applies to non-io events and is 10 minutes.

fstat intvl [lfn] [ops] [ssq] [xfr cnt]

Enables file activity monitoring using a special "**f**" stream. The *intvl* is the maximum time event data may be internally buffered before it is sent to the monitoring destination. Specify a number optionally suffixed by **h** for hours, **m** for minutes, or **s** for seconds. A value of zero disables the "**f**" stream. The *intvl* is also used as the basis for **xfr** event data. By default, only file open and close events are inserted into the stream. Additional information may be requested as follows:

- **lfn** includes the user's dictionary identifier along with the logical file name being opened in the open event record.
- **ops** includes detailed operation count information along with minimum and maximum values in the close event record.
- ssq includes the sum of squares count for read and write sizes in the close event record. Specifying ssq automatically includes ops. This option impacts server performance. See the notes for more information.
- **xfr** *cnt* inserts the number of bytes read and written from each open file every *intvl*cnt* elapsed time. The *cnt* must be 1 or more.

ident sec

The number of seconds between each server identity transmissions (i.e., the '=' map record). Specify a number optionally suffixed by **h** for hours, **m** for minutes, or **s** for seconds, the default. A value of zero transmits the identity only once at start-up time. Specifying **off** prevents identify records from being sent. The default is 1 hour (i.e. 3600 seconds).

fbuff size

the maximum size of the datagram for file and I/O events (i.e. the f–stream). Specify no less than 1024 and no more than 64k. The *size* can be suffixed by **k** to indicate **k**ilo-bytes. The default size is 64k.

gbuff size

the maximum size of the datagram for plug-in generated events (i.e. the gstream). Specify no less than 1024 and no more than 64k. The *size* can be suffixed by \mathbf{k} to indicate **k**ilo-bytes. The default size is 32k.

mbuff size

the maximum size of the datagram for all other events not covered by a specific x**buff** parameter. Specify no less than 1024 and no more than 64k. The *size* can be suffixed by **k** to indicate **k**ilo-bytes. The default size is 16k.

rbuff size

the maximum size of the datagram for redirection events (i.e. the r–stream). Specify no less than 2048 and no more than 64k. The *size* can be suffixed by **k** to indicate **k**ilo-bytes. The default size is 32k.

rnums cnt

the number of redirection monitoring streams to start. Specify no less than 1 and no more than 8. The default size is 3.

window intvl

The monitoring window size. Data collected within the window is not differentiated by time. Thus, the window represents the undifferentiated sampling interval. Specify a number optionally suffixed by **h** for hours, **m** for minutes, or **s** for seconds, the default. The default is 60 seconds.

dest events host:port

The *events* that are to be sent to the endpoint identified by *host:port*. All monitoring messages are sent as datagrams (i.e., **UDP** protocol). The **dest** parameter, if specified, must be specified as the last parameter. Up two destinations are allowed. By default, only file event information is sent. The permissible events are:

Event	Stream	Explanation	
ccm	g	cache context management information.	
files	t	file-related request monitoring (i.e., open and close	
		requests).	
fstat	f	specified "f" stream information (i.e., open and close	
		requests).	
io	t	I/O request monitoring (read and write requests plus	
		files).	
iov	t	same as io above plus details on readv vector elements.	
info	m	client specified monitoring data submitted using xrootd	
		protocol and other miscellaneous information.	
pfc	g	proxy file cache information (i.e. proxy disk caching).	
redir	r	redirection events.	
tcpmon	g	TCP connection statistics at time of socket close.	
user	f	client login and disconnect events.	

Defaults

```
flush 10m ident 1h fbuff 64k gbuff 32k mbuff 16k rbuff 32k \backslash rnums 3 window 60
```

Notes

- 1) Use the **monitor** directive to enable statistical gathering and reporting of events, file information, and I/O requests.
- 2) The monitor directive not only sets general parameters but is also used to enable monitoring streams whose events are sent with a common XRootD binary header. The header facilitates the use of a central collection, reformatting, and redistribution service.
- 3) Specifying the **dest** parameter enables the selected events to be sent to the specified endpoint. If **dest** is not specified, common header event monitoring is not enabled. You may, however, selectively enable alternative g-stream event monitoring using the **mongstream** <u>directive</u> even when other event monitoring is disabled.
- 4) The **fstat ssq** option impacts performance since floating point operations must be carried out for each read and write request in order to accurately compute the sum of squares. The counts can be used to compute the standard deviation for read and write sizes. Do not specify this option unless there is a clear need for such information.
- 5) The **fstat ssq** counts are available on platforms that use IEEE 754 floating point format. The **fstat ssq** option is ignored on non-conforming platforms.
- 6) The **io** option reports individual seeks for each read and write request. While this data may be used to determine access patterns or used in I/O trace simulation studies, it reduces server performance by about 7% and generates a large amount of monitoring data. Normally, **fstat** provides sufficient information about client I/O efficiency at a much lower cost.
- 7) The flush parameter does *not* apply to monitor streams that include io event data unless io is specified. By default, monitor streams that include io event data are flushed only when the internal monitor buffer becomes full or when the user owning the stream being monitored disconnects.
- 8) You may specify two monitoring destinations. This allows you to isolate data high volume streams (i.e., **io** monitoring) and provide real-time display for low-volume streams (i.e., **info**, **files**, **fstat**, and **user**). Also refer to the **mongstream** <u>directive</u> that provides for additional routing options.

- 9) The all option forces monitor data to be collected for all connections. If all is not specified, each client must enable monitoring manually using the xrootd set request code (see the xrootd protocol specification). This allows selective monitoring and gives each client the opportunity to tag io monitor data with the relevant application name.
- 10) The **iov** option inserts a read entry for every element in a **readv** vector. This may explode the amount of monitoring information that is generated. By default, when only **io** is specified, a summary **readv** entry is placed in the monitoring stream.
- 11) Clients cannot enable monitoring that has not been enabled by the **monitor** directive.
- 12) Specifying a small datagram buffer size (e.g. less than 8k) increases the number of datagrams that need to be sent and, consequently, adds to server overhead. Large datagram buffer sizes reduce the number of datagrams as well as server overhead but increase memory utilization as each connection allocates a buffer.
- 13) Approximately 61 requests can fit into a 1K mbuff.
- 14) On average, 64 to 128 redirection events can fit into a 32K rbuff.
- 15) Increasing the number of redirection monitoring streams (**rnums**) reduces the bottlenecks in the monitoring path.
- 16) Specifying a small window increases the timing accuracy of any individual request entry at the expense of additional datagrams and significantly increased server overhead. Conversely, large window sizes reduce timing accuracy but also reduce server overhead.
- 17) The g-stream events: ccm, pfc, and tcpmon are for events generated by specific plug-ins. The plug-ins are loaded by variouis directives.Specifying a g-stream whose associated plug-in has not been loaded is ignored. The g-stream events are:

Event	Plug-in Directive	Type of information reported
ccm	pss.ccmlib	Cache context management events.
pfc	pss.cachelib	Data caching events.
tcpmon	xrd.tcpmonlib	TCP connection statistics at disconnect.

18) Refer to the "XRootD Monitoring" reference for a detailed explanation on the datagram format used by the monitoring subsystem. It is especially important to understand the different between **files**, **fstat**, and **io** monitoring as the information overlaps and there is rarely a need to specify all three.

Example

xrootd.monitor all fstat 5m dest fstat datacoll:5050

7.9 prep

```
xrootd.prep parms
```

parms: [keep ksec] [scrub time] [logdir ldir]

Function

Specify how prepare request tracking is done.

Parameters

keep ksec

The time that prepare request tracking record are to be held. The time may be suffixed by **s** (the default), **m** , or **h** to indicate seconds, minutes, and hours, respectively. The default is 24 hours.

scrub time

The time between scrubs of the tracking log directory. The time may be suffixed by **s** (the default), **m**, or **h** to indicate seconds, minutes, and hours, respectively. The default is 1 hour.

logdir ldir

The absolute path of the directory that is to hold the preparation tracking records. A directory must be specified, otherwise preparation request tracking is disabled.

Defaults

None. Preparation request tracking is normally disabled. When a **logdir** directory is specified, the **keep** and **scrub** defaults of **24H** and **1H** apply, respectively.

Notes

 This directive allows server to track prepare requests. When request tracking is enabled, each prepare is logged in the **logdir** directory. It then becomes possible to list the requests and cancel them, if need be.

- 2) Since there can be more than one redirecting **xrootd** server, prepare requests may be scattered across several servers. It is the client's responsibility to collect information from each server in order to create a composite preparation request history.
- 3) Each server uniquely names the files in the **logdir** directory. When multiple **xrootd** redirecting servers exist, it is possible to collect full preparation history from any server, if the **logdir** directory is located in a shared file system (e.g., **NFS**).
- 4) When running multiple **xrootd** servers on the same machine, the instance name (-**n** command line option) is used to differentiate **logdir** directories among all instances by appending the instance name to the path.

Example

xrootd.prep keep 12H logdir /nfs/xrootd/preplog

7.10 redirect

Function

Specify request forwarding.

Parameters

- *target* The name or address of the *host* and *port* number where clients are to be redirected based on the subsequent parameters. The target consists of one or two *host:port* specifications with the second separated by a percent sign (%). When a second *host:port* is specified, then clients connecting using a private IP address are redirected to the second *host:port* while clients connecting with a public IP address are redirected to the first *host:port*. If only one *host:port* is specified, all clients are redirected to that host.
- *foper* Specifies which metadata operations are to be *immediately* redirected. One or more operations may be specified. The specifications are cumulative and processed left to right. Each operation may be optionally prefixed by a minus sign to turn off the setting. Valid operations are:

all	redirect all possible operations
chmod	redirect change mode requests
chksum	redirect checksum requests
dirlist	redirect directory content listing requests
locate	redirect path location requests
mkdir	redirect create directory requests
mv	redirect rename requests
prepare	redirect prepare requests that <i>do not need</i> file staging
prepstage	redirect prepare requests that <i>may need</i> file staging

rm	redirect file removal requests
rmdir	redirect directory removal requests
stat	redirect file attribute requests
trunc	redirect file truncate requests using a path

- *path* Specifies that when a file open request occurs on the specified path prefix, the client should be redirected to the specified host and port. One or more paths may be specified. However, no more than four different host-port combinations may be specified.
- *? path* Specifies that any client operation on the specified path prefix that ends with a "not found" error (i.e., **EONOENT**) and has not been specifically covered by another redirect directive, the client should be redirected to the specified host and port. All subsequently specified paths, if any, on the line fall under the "not found" provision.

Defaults

xrootd.redirect -all

Notes

- 1) Request redirection is typically applicable to the cluster manager. Refer to the **role** directive in the "Clustering Configuration Reference" for additional information, especially on inter-related directives.
- 2) Normally, meta-data requests are performed on the local host. However, certain clustered environments may be controlled by a central manager that records the exact state of every file. In such environments, the central manager may perform meta-data requests. When the **redirect** directive is not specified, the client is directed to perform the operation on a single host, normally the one that has the file. When the request is redirected, the target host is responsible for performing the operation.
- 3) The redirect path prefixes are always matched from most- to least-specific prefix (i.e., longest to shortest).

Example

xrootd.redirect all -prepare

7.11 tls

```
xrootd.tls [capable] req
```

```
req: [-]all | [-]data | [-]login | none | off |
```

```
[-] session | [-] tpc | req
```

Function

Specify transport layer security (TLS) requirement.

Parameters

capable

applies requirements only to **TLS** capable clients. The default is to apply **TLS** requirements to all clients irrespective of their ability to use **TLS**.

req specifies the general requests for which TLS must be used. Clients who attempt these requests without using a TLS connection are rejected with a "TLS Required" error message. Valid req are:

all	requires TLS for all requests
data	requires that all file data or metadata be transmitted using TLS
login	requires TLS for login requests and all subsequent requests
none	turns off all requirements (off is a synonym)
session	requires TLS for all requests <i>after</i> the login and authentication
tpc	requires TLS for third party copy requests

Defaults

xrd.tls none

Notes

- The capable parameter is meant to provide a migration path for pre-Release 5 clients (i.e. those that do not support TLS). Requiring TLS for all clients essentially disallows older clients from using XRootD.
- 2) The **tls** directive is cumulative and allows different settings for **TLS**capable clients and those that do not support **TLS**. See the examples on how to accomplish this.
- 3) Specifying a minus sign in front of any indicated requirement removes that requirement from the current set of requirements.

- 4) The **session** requirement is a subset of the **login** requirement. If both are specified, **login** prevails.
- 5) The **data** requirement applies to the session connection as well as any additional connections bound to the session. If **data** is specified without specifying **login** or **session**, **session** is automatically added to the requirements.
- 6) At least one requirement must be specified, even if it's **none** or **off**.
- 7) When **none** or **off** is encountered, all applicable requirements are discarded.
- 8) The requirements only apply to the **XRootD** protocol. They do not apply to any other protocols running in parallel with **XRootD**.
- 9) The **tls** directive fails if **TLS** has not been configured using the **xrd.tls** directive.

Example xrootd.tls tpc

The above requires that any third party copy request use a **TLS** connection. This also prohibits older client (i.e. those incapable of **TLS**) from requesting a third party copy. Adding the following directive

xrootd.tls capable session

also requires that **TLS** capable clients must use a **TLS** connection after the login and authentication phases. Note that while **session** also covers third party copy requests, the preceding directive requires that all **TPC** requests use **TLS**. Hence, non-capable clients can do anything they are allowed to do but cannot request a third-party copy.

7.12 trace

```
xrootd.trace [-]option [ [-]option ] [•••]
option: all | debug | emsg | fs | login | mem | off |
        pgcserr | pgread | pgwrite | stall | redirect |
        request | response
```

Function

Specify execution tracing options.

Parameters

option The tracing level. One or more options may be specified. The specifications are cumulative and processed left to right. Each option, other than **off**, may be optionally prefixed by a minus sign to turn off the setting. Valid options are:

all	selects all possible trace levels
debug	traces internal activities for debugging purposes
emsg	traces errors sent back to the client
fs	traces file system requests
login	traces login and authentication steps
mem	traces memory management functions
off	traces nothing
pgcserr	traces checksum errors encountered by pgwrite
pgread	traces pgread requests
pgwrite	traces pgwrite requests
stall	traces client deferrals due to resource limitations
redirect	traces client redirections to other servers
request	traces client request information
response	traces request response information

Defaults

xrootd.trace off

Notes

- 1) *Warning*: enabling tracing may reduce server performance by 50%!
- 2) All tracing is enabled when the daemon is invoked with the -d option.

3) All previous trace settings are discarded when **off** is encountered.

Example

xrootd.trace all -debug

8 Enabling HTTP Access

XRootD supports **HTTP** access via a protocol plug-in. The **HTTP** protocol can run alongside of standard **XRootD** protocol without any interference; providing an additional access mode. To Enable **HTTP** access, add the following configuration parameter to the configuration file.

```
if exec xrootd
xrd.protocol http[:port] path/libXrdHttp.so [cfgfile]
fi
```

Parameters

- *port* The port number http is to use for incoming requests. Specify a number, the name of a **TCP** service, or the word **any**. If you do not specify port number, port 1094 is used. This is also the default port for **XRootD** protocol.
- *path* The path to the shared library **libXrdHttp.so** that contains the code the implements the **HTTP** protocol.
- *cfgfile* is the path to an external configuration file specific to **HTTP**. If not specified, the configuration file at daemon start-up is used.

Defaults

Not applicable.

Notes

- You should surround the xrd.protocol directive with the shown if-fi if you are using a common configuration file for xrootd and cmsd daemons. Failure to do so will prevent the cmsd from starting.
- 2) All **HTTP** requests are bound by any "**xrd**." and "**xrootd**." Directives that exist in the start-up configuration file. Hence, **HTTP** access cannot exceed any restriction imposed by those directives.
- 3) Monitoring of HTTP requests is handled as if they are XRootD requests. Consequently, the monitoring stream includes all HTTP requests as well. However, monitoring information is tagged with the fact that the information was generated by the HTTP protocol.

- 4) While the default port number is the same as for **XRootD**; the framework directs each request to appropriate protocol and these requests are never intermixed. To avoid any confusion you may wish to use a more standard **HTTP** port number such as 8080. This is especially true if connection are made using **HTTPS**.
- 5) Additional configuration file directives specific to **HTTP** are always prefixed with "**http.**" and the following sections describe these directives.
- 6) **HTTP** support also includes **WebDav** support enabling a wider range of access abilities beyond simple get and post capabilities.
- 7) When **HTTP** is used in a clustered **XRootD** deployment, all servers in that deployment must have **HTTP** enabled. Failure to do so typically results in access failure when a client is redirected to a serer that holds the desired file but for which **HTTP** was not enabled.
- 8) Not all **HTTP** clients support all **HTTP** features. While the plug-in does not violate the **HTTP** or **WebDav** standards, it does implement a wide range of allowable features (e.g. redirection on POST requests) that may not be supported by the **HTTP** client being used.

8.1 Enabling HTTPS

When a server is configured to use **HTTPS**, each server processes the client's credentials from the connection. This allows the client to be authenticated and makes authorization possible. On the other hand, **HTTPS** is very resource demanding because it encrypts and decrypts all of the **TCP** traffic. Additionally, the process of establishing an encrypted connection requires several network interchanges that increase connection latency which can be substantial on a wide area network.

While **HTTP** is much faster it is impossible to authenticate the client using **HTTP**. However, the **HTTP** plug-in allows a client to initially connect with **HTTPS**, extract the authentication information, encode that information in a low-overhead encrypted security token and redirect the connection to use **HTTP**. This is known as **HTTPS** to **HTTP** conversion and is much less resource intensive. When a server is configured to do **HTTPS** to **HTTP** conversion, it always expects a security token to be present when a client connects via **HTTP**. If the token is missing or cannot be decrypted the connection is rejected. This mechanism provides a relatively secure authentication but at the expense of privacy as no traffic is encrypted past the authentication stage.

HTTPS to **HTTP** conversion is especially attractive in clustered environments where a client typically makes contact with a particular node (i.e. redirector) that then redirects the client to a particular server that holds the requested file. Using **HTTPS** everywhere incurs identical overhead at each contact point. This can be eliminated by using **HTTPS** at the initial contact point and converting **HTTPS** to **HTTP** for subsequent connections. This incurs the overhead just once.

When enabling **HTTPS** you should consider the following points:

- If only **HTTPS** is configured, then the server only accepts **HTTPS** connections (see the **xrd.tls** and **xrd.tlsca** directives).
- If **HTTPS** to **HTTP** conversion is configured a server accepts an **HTTPS** connection or an **HTTP** connection that provides a valid security token (see the **secretkey** directive)
- If self-conversion of HTTPS to HTTP is configured, the server unconditionally redirects any HTTPS incoming connections to itself; using HTTP and a security token (see the selfhttps2http directive). This allows greater performance for subsequent requests.

When using **HTTP** in an **XRootD** cluster, additional considerations apply on how the cluster redirector interacts with data servers in that cluster. The following table provides reasonable possibilities, depending on the degree of security that is desired.

Redirector Accepts	Server Accepts	Configuration	Remarks
HTTP	HTTP	The is the default	No security.
HTTPS	HTTP with	Specify xrd.tls ,	Central
	security token	xrd.tlsca and	authentication, fast
		http.secretkey	unencrypted data
		directives.	access but higher
			CPU load in the
			redirector
HTTP	HTTPS	Specify xrd.tls and	Fast redirection,
		xrd.tlsca directives	distributed
		only in data	authentication,
		servers. Specify	slow encrypted
		http.desthttps in	data access
		redirectors.	
HTTP	HTTPS with self	Specify xrd.tls ,	Fast redirection,
	redirection using	xrd.tlsca,	distributed
	HTTP with	http.selfhttps2http	authentication, fast
	security token	and http.secretkey	unencrypted data
		directives <i>only</i> in	access
		data servers.	
		Specify	
		http.desthttps in	
		redirectors.	
HTTPS	HTTPS	Specify xrd.tls and	Fully authenticated
		xrdtlsca directives	but authentication
		in servers and	occurs twice, slow
		redirectors.	encrypted data
			access, resource
			consumption can
			be high

8.1.1 Backward Compatibility and Overrides

Exceptions are handled by the **http.httpsmode** directive. See this directive on how to control backward compatibility warning messages.

8.2 Directives to Enhance HTTPS Access

By default, **HTTPS** access is not enabled. You must specify certain critical **xrd** information in order for **HTTPS** to be enabled (i.e. **xrd.tls** and **xrd.tlsca**).

The **xrd** framework provides **TLS** services to all protocols and **HTTPS** relies on these services. The **xrd.tls** and **xrd.tlsca** directives should be used to configure **TLS** for **HTTPS**. Previous releases relied on **http** specific directives to do this (i.e. **http.cadir**, **http.cafile**, **http.cert** and **http.key**). These are still accepted and still allow **HTTPS** to be configured. However, when specified a warning message is issued to remind you to use the **xrd** framework directives instead. It is best to configure **TLS** for all protocols using a common set of directives to avoid inconsistency. Therefore, the **http**-specific **TLS** directives have been deprecated.

However, there are other directives that are specifically oriented to improving the handling of **HTTPS**. These are described in the following sections.

8.2.1 desthttps

http.desthttps {no | yes}

Function

Specify whether or not HTTPS is to be used for redirections.

Parameters

- **no** A redirector will always redirect a client using http. The word **false** and the number **0** are synonyms.
- **yes** A redirector will always redirect a client using https. The word **true** and the number **1** are synonyms.

Defaults

http.desthttps no

Notes

1) While this directive applies normally applies to redirectors it is used by any node, redirector or data server that redirects a client.

Example

http.desthttps yes

8.2.2 gridmap

http.gridmap path

Function

Specify the file containing the "grid map file" that the server must use.

Parameters

path The path to the file.

Defaults

None.

Notes

- 1) This file is loaded at startup and used to translate the requestor's x509 DN into a short user name for internal authorization usage.
- 2) This directive requires that **HTTPS** be enabled with certificate verification.

Example

http.gridmap /etc/grid-security/mapfile

8.2.3 httpsmode

http.httpsmode {auto | disable | manual}

Function

Specify how to handle enabling HTTPS protocol.

Parameters

auto automatically enables the use of **HTTPS** if the underlying **xrd** framework was configured to allow **TLS** (i.e. the **xrd.tls** and **xrd.tlsca** directives). This is the default.

disable

disables the use of HTTPS regardless of any other directives.

manual

enables the use of **HTTPS** but requires that the appropriate **http** directives are used to specify required **HTTPS** parameters (i.e. **http.cadir**, **http.cafile**, **http.cert** and **http.key**).

Defaults

http.httpsmode auto

Notes

 When **auto** is in effect, you may still override **xrd** directives that are used for **HTTPS**. However, each override produces a warning message. To suppress the warnings specify **manual** and provide all the required **http** directives to configure **HTTPS**.

Example

http.httpsmode manual

8.2.4 secretkey

http.secretkey {path | token}

Function

Specify the key to be used to encrypt and decrypt redirection tokens.

Parameters

- *path* The absolute path to the file containing a random string of alpha-numeric characters and symbols that are to be used to encrypt and decrypt redirection tokens.
- *token* A random string of alpha-numeric characters and symbols that are to be used to encrypt and decrypt redirection tokens. The token may not start with a slash. Warning! Specifying the key in the configuration file exposes the key to theft whenever the configuration file is displayed!

Defaults

None.

Notes

- 1) The same key must be used by all nodes within a cluster.
- 2) Specifying a secret key automatically enables **HTTPS** to **HTTP** conversion.

Example

http.secretkey /admin/thekey

8.2.5 selfhttps2http

http.selfhttps2http {no | yes}

Function

Specify whether or not a server may redirect an **HTTPS** connection to itself using **HTTP** plus a security token.

Parameters

- no A server should continue to use HTTPS for all communications. The word false and the number 0 are synonyms.
- yes A server should convert an HTTPS session to an HTTP session by redirecting the client to itself using HTTP plus a security token. The word true and the number 1 are synonyms. You must also specify the secretkey directive.

Defaults

http.selfhttps2http no

Notes

- This option is meant to control the level of data privacy that is desired. Normally, HTTPS connections are converted to HTTP connections after authentication information is extracted from the HTTP stream. This greatly reduces overhead as no data past the authentication stage has to be encrypted.
- 2) When an **HTTPS** connection is converted to an **HTTP** connection, the redirection includes a security token encrypted with the key specified by with the **secretkey** directive. The **HTTP** connection is only accepted if the token can be decrypted using the same key.

Example

http.selfhttps2http yes

8.2.6 secxtractor

http.secxtractor path [parms]

Function

Specify the location of the specialized authentication information extractor plug-in.

Parameters

path The path to the shared library containing the plug-in.

parms The parameters to the shared library containing the plug-in.

Defaults

None.

Notes

- 1) A Security eXtractor plug-in is a component that can be loaded at initialization time in order to provide specialized processing to the certificate passed by the client. Normally, all authentication information comes from the standard part of the client certificate and any extensions are ignored. A Security eXtractor can be used to extract other information from the certificate or any of its extensions. This information is then passed along and may be used for other authorization functions within **XRootD**.
- 2) The typical case for which a security extractor library is needed is to extract the extended VO information from a Grid client's certificate.
- 3) A general purpose VO Security eXtractor plug-in is available with the **gsi** package that can be used with **HTTPS**. See the explanation of the **VOMS** plug-in in the security reference.
- 4) The **secxtractor** plug-in requires that **HTTPS** be enabled with certificate verification (i.e. **xrd.tlsca** or **http.cadir** or **http.cafile** be specified).

Example

http.secxtractor /usr/lib64/libXrdSecgsiVOMS.so

8.2.7 tlsreuse

http.tlsreuse off | on

Function

Specify transport layer security (TLS) session reuse characteristics.

Parameters

off disables the TLS session cache and may substantially increase latency for reconnecting clients. This is the default.

on enables the TLS session cache.

Defaults

http.tlsreuse off

Notes

- 1) The **https** protocol cannot successfully use the **TLS** session cache when it needs to handle **TLS** peer certificates. This is why the default is off.
- 2) The cache is flushed every 255 connection which is not ideal but the mechanism **OpenSSL** uses.

8.2.8 Deprecated HTTPS Directives

8.2.8.1 cadir

http.cadir path

Function

Specify the directory containing the CA certificates (see the **cafile** directive as an alternative).

Parameters

path The path to the directory.

Defaults

None.

Notes

- 1) Replace this directive with **xrd.tlsca** to configure all protocols to use the same certificate directory.
- 2) All of the certificates in the directory must be in a format that is recognized by the version of **OpenSSL** is being used.
- 3) If the certificate information is contained in a single file, you should either use the **xrd.tlsca certfile** (*preferable*) or the **http.cafile** directive.

Example

```
http.cadir /etc/grid-security/certificates
```

8.2.8.2 cafile

http.cafile path

Function

Specify the file containing the CA certificates.

Parameters

path The path to the file.

Defaults

None.

Notes

- 1) Replace this directive with **xrd.tlsca certfile** to configure all protocols to use the same certificate file.
- 2) All of the certificates in the file must in a format that is recognized by the version of **OpenSSL** is being used.
- 3) If certificates are contained in multiple files you should use the **xrd.tlsca certdir** (*preferable*) or the **http.cadir** directive.

Example

http.cafile /etc/myCA.pem

8.2.8.3 cert

http.cert path

Function

Specify the file containing the x.509 certificate that the server must use.

Parameters

path The path to the file.

Defaults

None.

Notes

- 1) Replace this directive with **xrd.tls** to configure all protocols to use the same certificate.
- 2) The certificate must be in **PEM** format.
- 3) See the related **http.key** directive to specify the location of the private key.

Example

http.cert /etc/grid-security/hostcert.pem

8.2.8.4 cipherfilter

http.cipherfilter ciphers

Function

Specify the allowed ciphers for transport layer security (TLS).

Parameters

ciphers

A list of colon separated ciphers that are allowed to be used.

Defaults

For **OpenSSL** versions greater than 1.0.2 the ciphers recommended by mozilla.org version 5.4 guidelines are used. These are strict ciphers. For older **OpenSSL** versions, generic ciphers are used for compatibility reasons.

Notes

- 1) Replace this directive with **xrd.tlscipher** to configure all protocols to use the same ciphers.
- 2) The **http.cipherfilter** directive is provided in cases where a default cipher has been shown to be insecure and should be removed. In this case, you need to specify all of the ciphers less the one you wish to eliminate.

Example

http.cipherfilter ALL:!LOW:!EXP:!MD5:!MD2

8.2.8.5 key

http.key path

Function

Specify the file containing the x.509 private key that the server must use.

Parameters

path The path to the file.

Defaults

None.

Notes

- 1) Replace this directive with **xrd.tls** to configure all protocols to use the same certificate key.
- 2) The key must be in **PEM** format.
- 3) See the related **http.cert** directive to specify the location of the server's certificate.
- 4) Specifying a key without specifying a certificate location is inconsistent and causes the key specification to be ignored along with a warning message.

Example

http.key /etc/grid-security/hostkey.pem

8.3 Common Directives

8.3.1 embeddedstatic

http.embeddedstatic {no | yes}

Function

Specify where **CSS** template and logo is to come from for formatted listings.

Parameters

- **no** The CSS template and logo information must be over-ridden by another file containing such information. The word **false** and the number **0** are synonyms.
- **yes** An internal memory-based CSS template and logo should be used. The word **true** and the number **1** are synonyms.

Defaults

http.embeddedstatic yes

Notes

- 1) Using the default memory-based CSS template and logo provide much better performance and makes the setup much simpler.
- 2) If you need to use a custom style sheet, significant performance gains can be achieved by preloading the style sheet file using the **staticpreload** directive.

Example

http.embeddedstatic yes

8.3.2 exthandler

http.exthandler name path [token]

Function

Specify the location of the **TCP** connection statistics monitoring plug-in.

Parameters

name a 1- to-16 character unique name identifying the handler.

- *path* The absolute path to the shared library that contains an implementation of the handler.
- *token* An optional parameter to be passed to the plug-in object creation function. Typically, this is the name of a configuration file.

Defaults

None.

Notes

- 1) Each exthandler is invoked for every **HTTP** request to allow special handling for certain requests.
- 2) No more than 4 handlers may be loaded.

Example

http.exthandler mhandler17 /opt/http/lib/libExtHndlr.so

8.3.3 header2cgi

http.header2cgi hdrkey cgikey

Function

Specify which headers are to be promoted to **cgi** information and appended to the incoming **url**.

Parameters

hdrkey the header key that is to be promoted to cgi information.

cgirkey the cgi key name that the promoted header should have.

Defaults

None.

Notes

- Normally, header information is internally processed and not made available to other plug-ins. The **header2cgi** directive allows you to pass on header information to external plug-ins via the incoming **url** by promoting the header payload to a **cgi** element.
- 2) Assuming *xyzzy* is the payload of header with a key of **auth**, the example shown below would promote the header by appending "**authz=***xyzzy*" to the incoming **url** as **cgi** information before it is passed to other system components. This essentially makes the header visible outside of the **http** plug-in.
- 3) The **header2cgi** directive is meant to be used for non-**http** plug-ins that wish to consider specific information sent via the **http** protocol.

Example

http.header2cgi auth authz

8.3.4 listingdeny

http.listingdeny {no | yes}

Function

Specify whether or not directory listings are allowed.

Parameters

- **no** Directory listings are not allowed. The word **false** and the number **0** are synonyms.
- **yes** Directory listings are allowed. The word **true** and the number **1** are synonyms.

Defaults

http.listingdeny no

Notes

- 1) In a clustered environment a listing of a directory via **HTTP** only lists the directory of some arbitrary server in the cluster. Since files are scattered across all of the servers in the cluster; this likely produces an incomplete listing. You may wish to deny directory listings to avoid confusion.
- 2) Alternatively, you can redirect directory listings to a special node that can produce a composite listing using all nodes in the cluster via the **listingredir** directive.
- 3) Note that the **XRootD** based **xrdfs** command automatically produces a composite listing.

Example

http.listingdeny yes

8.3.5 listingredir

http.listingredir desturl

Function

Specify the node to which to redirect clients requesting a directory listing.

Parameters

desturl The redirection URL to use when a directory listing is requested.

Defaults

None.

Notes

None.

Example

http.listingredir http://hostwhichprovideslistings:80/

8.3.6 staticpreload

http.staticpreload url path

Function

Preload a static resource file into memory.

Parameters

url The URL naming a static resource (e.g. style sheet or icon).

path The path to the local file containing the resource.

Defaults

None.

Notes

- 1) Static resources named in a URL must start with "/static" in order to be recognized.
- 2) The contents of the static resource contained in path may not exceed 64K. If it does, it is truncated to 64K.
- 3) Typical static resources are URL resources ending with ".css" and ".ico".
- 4) This directive is ineffective if the **staticredir** directive is specified.

Example

http.staticpreload http://static/mycss.css /etc/mycss

8.3.7 staticredir

http.staticredir newurl

Function

Preload a static resource file into memory.

Parameters

newurl The URL the client is to be redirected to when requesting a non-local or unsupported static resource.

Defaults

None.

Notes

1) The **staticredir** directive is only effective when a) **embeddedstatic** processing is disabled, or b) the resource is neither a content style sheet nor an icon.

Example

http.staticredir <u>http://althost/</u>

8.3.8 trace

http.trace [-]option [[-]option] [•••]

```
option: all | debug | none | off | request | response
```

Function

Specify execution tracing options.

Parameters

- *option* The tracing level. One ore more options may be specified. The specifications are cumulative and processed left to right. Each option may be optionally prefixed by a minus sign to turn off the setting. Valid options are:
 - allselects all possible trace levelsdebugtraces internal activities for debugging purposesnonetraces nothingoffa synonym for nonerequesttraces client request information
 - **response** traces request response information

Defaults

Tracing is disabled.

Notes

- 1) All tracing is enabled when the daemon is invoked with the **-d** option.
- 2) All previous trace settings are discarded when **none** or **off** is encountered.
- 3) Tracing seriously degrades server performance. Use this directive *only* for debugging purposes.

Example

http.trace all -debug

9 Document Change History

14 March 2005

- Remove documentation on local redirection mode.
- Remove documentation of **-s** command line option.
- Add '-t' option to the StartXRD documentation.
- Significantly change the **port** directive, adding "**port any**" and "**if**".
- Discuss using "**port any**" mode.

26 April 2005

• Further clarified the **xrootd monitor flush** parameter.

1 June 2005

- Added description of conditional directives (if-fi).
- Added description of the **–n** command line option.
- Fully explain which run-time files are created.
- Deprecate –**r**, –**t**, and –**y** command line options.
- Deprecate the **XRDMODE** variable and remove the description of the **XRDTYPE** variable in the **StartXRD.cf** script.
- Remove extraneous options from the **StartXRD** script.

1 Aug 2005

- Document administrative interface portal socket.
- Add file size to open monitor record.

16 Aug 2005

• Add authentication mapping (a-record) to monitoring data.

6 Jan 2006

- Document the **-b** and **-R** command line options.
- Document how to independently bind different port numbers to available protocols.

25 Jan 2006

• Add max option to **chksum** directive.

22 March 2006

• Add exec condition to if/else/fi.

28 February 2007

- Cleaned up documentation relative to **role** directive and **all** prefix modifier.
- Documented the **xrootd.redirect** directive.
- Removed the **xrd.connections** directive.
- Placed most **xrd** directives in esoteric status.

28 March 2007

- Move conditional directives to a separate manual.
- Indicate the **adminpath** now is configured via the **all** prefix.
- Documented the xrd **wan network** and **protocol** directive option.
- Indicate that the **xrootd export** directive is configured via the **all** prefix and accepts **oss** options.

01 October 2007

• Document the **locate** option of the **redirect** directive.

01 January 2008

• Remove references to olbd.

01 February 2008

• General clean-up.

11 April 2008

• Document staging ('s') monitor record.

29 May 2008

• Document the **xrootd async nosf** option.

21 July 2008

- Document the **xrd network [no]dnr** option.
- Document the **xrd async minsfsz** option.

6 March 2009

• Document the **xrootd monitor stage** option.

22 June 2009

• Document the **xrd.report** directive.

7 July 2009

- Document the **mpxstats** command for monitoring.
- Document the summary variables.

17 March 2010

- Document the **timeout hail** and **kill** options.
- Document the pid file creation and the **pidpath** directive.

8 March 2011

- Document the **-s** command line option.
- Minor editorial changes.

24 May 2011

• Document the **auth** option in the **xrootd.monitor** directive.

31 May 2011

• Change the **xrootd.chksum** directive to support native checksums. Additional wording added explaining native checksums.

29 June 2011

• Document the **rbuff** and **redir** options on the **xrootd.monitor** directive to support redirection monitoring.

27 September 2011

• Document the **io flush** option on the **xrootd.monitor** directive.

----- Release 3.1.0

10 October 2011

• Document the **iov**, **migr**, and **purge** options on the **xrootd.monitor** directive.

2 November 2011

• Update documentation on the **xrootd.redirect** directive. It now accepts additional file operations (**chksum** and **trunc**), **open** targets (previously undocumented feature), and **ENOENT** targets.

3 December 2011

- Remove the **migr**, **purge** and **stage** options from the **xrootd.monitor** directive. These have been moved to the **frm.all.monitor** directive.
- Document the new **ident** option on the **xrootd.monitor** directive.

12 December 2011

- Document the **rnums** option for the **xrootd.monitor** directive.
- ----- Release 3.2.0
- ----- Release 3.2.1
- ----- Release 3.2.2
- ----- Release 3.2.3
- ----- Release 3.2.4

21 September 2012

- Document the **fstat** option for the **xrootd.monitor** directive.
- Remove the **rootd** configuration section.

----- Release 3.2.5

22 October 2012

- Document the **-S** command line option and the **all.sitename** directive for specifying a monitoring site name.
- ----- Release 3.2.6
- ----- Release 3.2.7

15 December 2012

• Change the **fstat sdv** option to **fstat ssq** in the **xrootd.monitor** directive.

 Release	3.3.0

- ----- Release 3.3.1
- ----- Release 3.3.2
- ----- Release 3.3.3
- ----- Release 3.3.4
- ----- Release 3.3.5
- ----- Release 3.3.6

11 February 2013

• Enhance the **fslib** directive to allow one to easily wrap one library with another.

23 February 2013 (IPV6 Introduction)

- Document the –I command line option.
- Document the **cache** option in the **xrd.network** directive.

12 August 2013

- Document the extended **–k**, **–l** and **–z** command line options.
- Document exported environment variables.
- Document the environment information file contents.
- General clean-up and better explanations.

2 December 2013

• Document the **xrootd.diglib** directive.

8 January 2014

- Document the **routes** option on the **xrd.network** directive.
- Document enhanced **xrootd.redirect** directive that can distinguish between public and private IP addresses.

18 February 2014

• Restrict the **routes** option on the **xrd.network** directive to prohibit autodiscovery of interface addresses as this may lead to choosing the wrong addresses.

27 March 2014

- Document how to enable **HTTP** and **HTTPS** protocols.
- Redesign the **routes** option on the **xrd.network** directive to cover the most common case.

6 August 2014

- Document the core option in the **xrd.sched** directive.
- Document how to export object identifier names via the **all.export** directive.

8 September 2014

- Document that **TCP keepalive** is now the default setting.
- Add a **nokeepalive** option and a **kaparms** option to the **xrd.network** directive.
- Indicate the **use** option in **xrd.network** accepts one or two interface names.
- Minor corrections to HTTP section.
- Document the http.mapfile, http.staticredir, http.staticpreload, and the http.trace directives.

27 September 2014

- Document multiple checksum support via the **xrootd.chksum** directive.
- Document the **default** option on the **xrootd.seclib** directive.
- Document the –L command line option.

26 November 2014

• Document the version option in the **xrootd.fslib** directive.

10 February 2015

- Document how to pass command line arguments to plug-ins.
- Document how to enable **digFS** but prevent its use until needed.

25 November 2015

• Explain the side-effects of the **-s** command line option on the placement of the environmental file.

15 April 2016

• Document log file plug-ins.

20 June 2016

- Document the **cse** parameter for logging plug-ins.
- Document the **xrd.network** [**no**]**rpipa** option.

10 March 2017

• Correct **http.mapfile** directive (it's really **gridmap**).

20 May 2017

• Document the **xrootd.fsoverload** directive.

27 October 2017

• Document the **http.header2cgi** directive.

19 December 2018

• Document the **xrd.tls** and the **xrootd.tls** directives.

31 May 2019

• Document the **xrd.tlsca** directive.

21 June 2019

- Document the **dyndns** option in the **xrd.network** directive.
- Remove all references to the **wan** option. It is no longer supported.
- Documented the **xrd tls network**, **port**, and **protocol** directive option.
- Correct spelling **of xrootd.async segsize** option (was **segsz**).

18 October 2019

• Document the preferred version of the **xrootd.fslib** directive.

21 December 2019

• Document the interaction between the **dyndns** and **cache** option of the **xrd.network** directive.

31 March 2020

• Document the **xrd.tlsciphers** directive.

11 April 2020

- General cleanup with better descriptions.
- Document the **ccm**, **pfc**, and **tcpmon** options of the **xrootd.monitor** directive.
- Document the **xrd.tcpmonlib** directive.
- Document the **http.cipherfilter** and **http.exthandler** directives.

14 April 2020

- Document the **-a** and **-A** command line options.
- Document the **xrd.homepath** and **xrd.tcpmonlib** directives.

24 April 2020

- Document the **xrd.trace** directive's **tls**, **tlsctx**, **tlsio**, and **tlssok** options.
- Document the **xrd.tlsca refresh** option.
- Document the **detail** and **cache** options of the **xrd.tls** directive.
- Document the **http.httpsmode** directive.

28 April 2020

- Remove the **xrd.tls** directive's **cache** option.
- Document the **xrd.tlsca** directive's **crlcheck** and **[no]proxies** options.
- Document changes in the **http.httpsmode** directive where **enable** has changed to **manual**.
- Re-factor the **http** protocol section and describe the deprecated directives.
- Document how the **TLS** session cache has, by default, turned off.
- Document the **xrootd.tlsreuse** directive.

5 May 2020

- Add directives by category for **xrd** and **xrootd** section.
- Cleanup **HTTP** section.

23 July 2020

- Remove documentation of the **xrootd.tlsreuse** directive.
- Add documentation for the **http.tlsreuse** directive.

20 August 2020

- Document the **xrootd.monitor** directive triple dot, **fbuff** and **gbuff** parameters.
- Document that the **xrootd.monitor** directive **dest** parameter is now optional.
- Add documentation for the **xrootd.mongstream** directive.

29 December 2020

• Document the **+port** option of the **xrd.protocol** directive.

6 January 2021

• Add admonition that using an external checksum agent via the **xrootd.chksum** directive disables returning checksums in a directory listing.

16 March 2021

• Document the **pgcserrs**, **pgread**, and **pgwrite** options of the **xrootd.trace** directive.