

# **Configuration File Syntax**

14 August 2015 Andrew Hanushevsky



Scalla: Structured Cluster Architecture for Low Latency Access ©2004-2015 by the Board of Trustees of the Leland Stanford, Jr., University All Rights Reserved Produced under contract DE-AC02-76-SFO0515 with the Department of Energy This code is open-sourced under a GNU Lesser General Public license. For LGPL terms and conditions see <u>http://www.gnu.org/licenses/</u>

1 Introduction			5	
		ecifying Conditional Directives		
	-	sing set Variables		
		Assigning Variable Values		
	3.2	Substituting Variables		
	3.3	Specifying set Options	15	
		Assigning Environmental Variable Values		
4	D	ocument Change History	17	

# 1 Introduction

This document describes the syntax used in the configuration file for **xrootd**, **cmsd**, and all other related components. Refer to the respective configuration documents on directive details.

All configuration directives start with a prefix identifying the system component to which the directive applies. The prefix is separated by the actual directive keyword by a single period. This allows configuration of all aspects of a system using a single configuration file. The following table lists valid prefixes

Prefix	System Component
acc	Access control (i.e., authorization)
cms	Cluster Management Services
dig	The <b>digFS</b> built-in file system
frm	File Residency Manager
http	HTTP protocol plug-in.
ofs	Open file system coordinating acc, cms & oss components
oss	Open storage system (i.e., file system implementation)
pfc	Proxy File Cache plug-in
pss	Proxy Storage Service plug-in
sec	Security authentication
xrd	Extended Request Daemon
xrootd	The <b>xrootd</b> protocol implementation.
all	Applies the directive to all of the above components.

*Records that do not start with a recognized identifier are ignored.* This includes blank record, comment lines (i.e., lines starting with a pound sign, #), and prefixes not immediately followed by a single period. Because each component has a unique prefix, a common configuration file can be used for the whole system. The location of the configuration file is specified on the command line. Refer to the reference manuals for each component on how it locates the configuration files.

This guide documents the basic directive syntax and describes the use of conditional statements and set variables within the configuration file.

# 2 Specifying Conditional Directives

The **if-fi** directives are used to allow you to optionally include directives based on host and instance name. The syntax for this directive pair is:

```
if [ hostpat [. . .] ] [ conds ]
     [ directives when if is true ]
[ else if [ hostpat [. . .] ] [ conds ]
     [ directives when all previous if's are false
                            and this if is true ]
]
     [ additional "else if" clauses, as desired ]
•
[ else
     [directives when all previous if's are false ]
]
  fi
hostpat: host | host+ | pfx* | *sfx | pfx*sfx]
conds: cond1 | cond2 | cond3
cond1: defined var [. . .] [&& {cond1 | cond2 | cond3}]
cond2: exec pgm [. . .] [&& cond3]
cond3: named name [. . .]
var: ?varname | ?~varname
```

### Function

Specify the conditions under which subsequent directives are to be used.

### Parameters

### hostpat

The pattern of the host to which subsequent directive applies. All nonapplicable hosts ignore all directives until the next **else** or **fi**. Host patterns are:

- *host* Any host that matches the specified **DNS** name.
- *host*+ Any host that has an address that matches any of the addresses assigned to host.
- $pfx^*$  Any host starting with pfx.

\**sfx* Any host ending with *sfx*.

*pfx\*sfx* Any host beginning with *pfx* and ending with *sfx*.

- *name* An instance name (i.e., a name that can be specified using the **–n** command line option). All directives until the next **else** or **fi** are ignored unless the executable has been given one of the instance names in the list of names.
- *pgm* The prefix-name of the executable. The prefix-name is defined to be all of the characters in the base filename (i.e., the directory path removed) up to but not including the first dot in the name, if any. If the name starts with a dot, the prefix-name is the complete base filename. All directives until the next **else** or **fi** are ignored unless the executable has the given name.
- var A set variable name or an environmental variable name, varname. "?varname" refers to set variable; while "?~varname" refers to an environmental variable.
   All directives until the next else or fi are ignored unless one of the specified variables in the list of variables is defined.

### Defaults

None. At least one *hostpat*, **defined**, **exec** or the **named** keyword must be specified.

### Notes

- All specified conditions must be true (i.e., *hostpat*, **defined**, **exec**, and **named**) for the subsequent directives to be used.
- A double ampersand (&&) is used to "and" two or more *named* tests. Be aware that the specified *named* tests must appear in the specific order (i.e. defined before exec and exec before named).
- 3) A qualified if is an **if** that is preceded by an else on the same line. An unqualified if is an **if** that appears first on a line.

- 4) Every unqualified **if** must be followed by a **fi**. Every **fi** must be preceded by a qualified or unqualified **if**.
- 5) Every **else** must be preceded by a qualified or unqualified **if**.
- 6) Nested unqualified **if** directives are not allowed.
- 7) The name **anon** refers to servers that were not given a name via **–n**.
- 8) Some directives allow the "if" to be placed as the rightmost tokens on the associated directive line. For these directives, no "fi" is required as the end of the line determines the **if**'s scope.

### Examples

```
if *slac.stanford.edu named anon
xrd.port 9999
fi
if named public
xrd.port 8888
else
xrd.port 9999
fi
if exec cmsd && named public
xrd.port 2131
else
xrd.port 1094
fi
if exec cmsd && named public
xrd.port 2131
else if exec cmsd && named private
xrd.port 3121
else
xrd.port 1094
fi
if defined ?~EXPORTPATH
set exportpath = $EXPORTPATH
else
set exportpath = /tmp
fi
all.export $exportpath
```

## 3 Using set Variables

### 3.1 Assigning Variable Values

```
set var = { value | varname }
varname: $envvar | $(envvar) | ${envvar} | $[envvar]
```

### Function

Specify the value a set variable must have.

### Parameters

- *var* The name of a variable. Variable names may only contain letters and digits and should start with a letter. Case is significant. Variable names may not be longer than 63 characters.
- *value* The value to be assigned to the variable. It must consist of a single non-blank text token no longer than 511 characters.

#### varname

The value comes from an environmental variable named *envvar*. The environmental variable must not be longer than 511 characters. In most cases the environmental variable must be defined, as explained below.

Specification	<b>Defined</b> envvar	Undefined envvar
\$envvar	Definition substituted	Fatal error
\$(envvar)	Definition substituted	Fatal error
<b>\$</b> {envvar}	Definition substituted	Fatal error
<b>\$[</b> envvar]	Definition substituted	Null string substituted

#### Notes

1) Unless **\$**[*envvar*] notation is used; use of an environmental variable that has not been set is considered to be a fatal error.

#### Example

set myVar = myToken set yourVar=\$EnvVar

### 3.2 Substituting Variables

```
1<sup>st</sup>_token subs
subs: [vname][text][subs]
vname: $var | ${var} | $(var) | $[var]
```

### Function

Specify a variable to be substituted by its set value.

### Parameters

1<sup>st</sup>\_token

The first token in any line of a configuration file. The first token may never specify a variable and is one of the following:

- A prefixed directive
- if, else, or the token fi
- set
- # (indicating a comment)

### *text* Any text.

*vname* The name of a set variable. The variable name ends when an nonalphanumeric character is encountered; including the of the line. The variable's value replaces name, as follows:

Specification	Defined envvar	Undefined envvar
\$envvar	Definition substituted	Fatal error
\$(envvar)	Definition substituted	Fatal error
<b>\$</b> {envvar}	Definition substituted	Fatal error
<b>\$[</b> envvar]	Definition substituted	Null string substituted

Notes

- 1) Except for **\$**[*envvar*]; use of a variable that has not been set is considered to be a fatal error.
- 2) Variables may be used in any text line other than a **set** statement.
- 3) Substitution occurs only once. Substituted lines are never rescanned.

### Example

```
set myHost = io.slac.stanford.edu
set myPath = /foo/fum/fi/
all.role manager if $myHost
ofs.fslib $(myPath)libXrdOfs.so
```

### 3.3 Specifying set Options

set {  $-\mathbf{q}$  |  $-\mathbf{v}$  |  $-\mathbf{v}$  }

#### Function

Specify the level of substitution detail.

### Parameters

-q Enables quiet mode. Neither substitutions nor substituted lines are displayed.

- -v Enables verbose mode. While substitutions are not displayed; substituted lines are displayed. This is the default.
- -V Enables very verbose mode. Both substitutions and substituted lines are displayed.

### Defaults

set -v

### Notes

- Configuration files are processed by multiple components. Every time a component scans through a configuration file and "-v" is in effect, substituted lines used by that component are displayed.
- 2) When "-V" is in effect, every time a variable is given a value the assignment is displayed. This means that each component scanning through the configuration file will generate a display of all set statements.

### Example

set -V

### 3.4 Assigning Environmental Variable Values

```
setenv envvar = { value | varname }
```

```
varname: $var | $(var) | ${var} | $[var]
```

### Function

Specify the value a environmental variable must have.

### Parameters

- *envvar* The name of an environmental variable. Variable names may only contain letters and digits and should start with a letter. Case is significant. Environmental variable names may not be longer than 63 characters and may not start with XRD.
- *value* The value to be assigned to the environmental variable. It must consist of a single non-blank text token no longer than 511 characters.

#### varname

The value comes from a set variable named var. In most cases the set variable must be defined, as explained below.

Specification	<b>Defined</b> envvar	Undefined envvar
\$var	Definition substituted	Fatal error
<b>\$(</b> var)	Definition substituted	Fatal error
<b>\$</b> { <i>var</i> }	Definition substituted	Fatal error
<b>\$[</b> var]	Definition substituted	Null string substituted

#### Notes

1) Unless **\$**[*var*] notation is used; use of an environmental variable that has not been set is considered to be a fatal error.

### Example

```
setenv EnvVar = myToken
set myPath = /foo/fum/fi/
setenv EnvPath = $[myPath]
```

# 4 Document Change History

### 29 March 2007

• Manual introduced.

### 8 January 2008

• Deprecate the **odc** and **olb** components.

### 23 June 2009

• Document the new "if/else if/else/fi" construct.

### 13 November 2010

- Document the new "**setenv**" construct.
- Allow undefined variables to be used via the **\$[]** construct.
- Remove references to the **odc** and **olb** components.

### 4 May 2014

- Document the new **defined** if-test construct.
- Add **http** as a component name.

### 14 August 2015

- Add missing components to the component table (i.e. **dig**, **frm**, **pfc**, and **pss**).
- Explain the use of the double ampersand.